



OCSPd (legacy)

Version 3.1.3, 2025-06-20

Table of Contents

1. Installation	1
1.1. Introduction	1
1.2. Pre-requisites	1
1.3. Installation Procedure	2
1.4. Configuration procedure	3
1.5. Running as container	22
1.6. Initial OCSPd Access	25
1.7. Uninstallation Procedure	27
2. Admin guide	28
2.1. Introduction	28
2.2. NGINX Specific Configurations	29
2.3. Initial Management Console Access and Logout	34
2.4. Administrator Profile	38
2.5. Managing Administrators	41
2.6. Managing Roles	53
2.7. Managing Hardware Security Modules	59
2.8. Managing Certificate Authorities	78
2.9. Managing OCSP Signers	93
2.10. Managing Services	112
2.11. Backup and Restore	113
2.12. Logs & Monitoring	116
2.13. HTTP Proxies	121
2.14. Key Performance Indicator(s)	127
2.15. Consuming the OCSP service	130
3. ELK integration	130
3.1. Introduction	130
3.2. ELK for EverTrust OCSP description	131
3.3. Logs agents' configuration	132
3.4. Logstash configuration	135
3.5. Kibana configuration	136
3.6. Index details	138

1. Installation

1.1. Introduction

Description

OCSPd (OCSP daemon) is an OCSP responder compliant with the following RFCs:

- RFC 6960
- RFC 5019

This project is powered up by:

- Akka
- BouncyCastle
- EHCache
- H2 Database
- IAIK PKCS#11 Wrapper
- Kamon
- Play! Framework
- Scala
- NGINX

This document is specific to OCSPd version **3.1.3**.

Scope

This document is an installation procedure detailing how to install and bootstrap OCSPd on a server running **CentOS/RHEL 6.x/7.x/8.x x64**.

Out of Scope

This document does not describe how to configure and operate an OCSPd instance. Please refer to the administration guide for administration related tasks.

1.2. Pre-requisites

This section describes the system and software pre-requisites to install OCSPd.

Hardware pre-requisites

The minimum requirements for running OCSPd are:

- 2 CPU cores;
- 8 GB of RAM;
- 500 GB of free disk space.

System pre-requisites

The following elements are considered as system pre-requisites:

- A server running CentOS / RHEL [6-7-8].x x64 with the network configured;
- Access with administrative privileges (root) to the server mentioned above;
- The IP address / DNS Name of one or several NTP server(s);
- The IP address / DNS Name of an SMTP relay;
- The email address of the OCSPd server administrator.

Software pre-requisites

The following elements are considered as software pre-requisites:

- The OCSPd installation package: `ocspd-3.1.3.noarch.rpm`;
- The NGINX installation package: `nginx-latest.el8.ngx.x86_64.rpm` (latest version of the nginx web server);
- Java 11: The latest Java 11 OpenJDK package (will be installed as a dependency of OCSPd but may required when working offline);

1.3. Installation Procedure

1.3.1. Installing NGINX

1. Upload the file `nginx-latest.el8.ngx.x86_64.rpm` through SCP under `/root`;
2. Access the server through SSH with an account with administrative privileges;
3. Install the NGINX web server using the following command:

```
yum localinstall /root/nginx-latest.el8.ngx.x86_64.rpm
```

4. Enable NGINX to start at boot using the following command:

```
systemctl enable nginx
```

5. Stop the NGINX service with the following command:

```
/etc/init.d/nginx stop
```

1.3.2. Installing the rngd service

1. Access the server through SSH with an account with administrative privileges;
2. Install the `rng-tools` package with the following command:

```
yum install rng-tools
```

3. Configure the `rngd` service with the following command:

```
echo 'EXTRAOPTIONS="-i -o /dev/random -r /dev/urandom -t 10 -W 2048"' >  
/etc/sysconfig/rngd
```

4. Enable and start the `rngd` service:

```
systemctl enable rngd  
systemctl start rngd
```

1.3.3. Installing OCSPd

1. Upload the file `ocspd-3.1.3-1.noarch.rpm` through SCP under `/root`;
2. Access the server through SSH with an account with administrative privileges;
3. Install the OCSPd package with the following command:

```
yum localinstall /root/ocspd-3.1.3-1.noarch.rpm
```



Installing the OCSPd package will install the following dependencies:

- `dialog`
- `java-11-openjdk-headless`

1.4. Configuration procedure


Configuring the NTP server(s)

Step 1: Access the server through SSH with an account with administrative privileges;


Step 2: Load the OCSPd Configuration Utility with the following command:

```
# /opt/ocspd/sbin/ocspd-config
```


Step 3: In the main menu, select 'NTP':



Step 4: Specify the list of NTP server(s) separated by ',' and validate:



Step 5: The NTPs configuration is updated:



Step 6: Exit the configuration utility and restart the NTPd service with the following command:

```
# /etc/init.d/ntpd restart
```


Configuring the SMTP Relay

Step 1: Access the server through SSH with an account with administrative privileges;


Step 2: Load the OCSPd Configuration Utility with the following command:

```
# /opt/ocspd/sbin/ocspd-config
```

Step 3: In the main menu, select 'SMTP':



Step 4: Specify IP address or the DNS name of the SMTP relay and validate:



Step 5: The Postfix configuration is updated:



Step 6: Exit the configuration utility and restart the Postfix service with the following command:

```
# /etc/init.d/postfix restart
```


Configuring the OCSPd Administrator's Email Address

Step 1: Access the server through SSH with an account with administrative privileges;


Step 2: Load the OCSPd Configuration Utility with the following command:

```
# /opt/ocspd/sbin/ocspd-config
```

Step 3: In the main menu, select '**Administrator**':



Step 4: Specify the email address of the OCSPd Administrator and validate:



Step 5: Exit the Configuration Utility;

Step 6: Validate the SMTP relay and Administrator Email Address with the following commands:

```
# yum install mailx
```

```
# mail -s "Hello OCSPd" root
> Hello From OCSPd
.
```

Step 7: Ensure that the email defined step 4 receives the test email.


Configuring the Radius Server

Step 1: Access the server through SSH with an account with administrative privileges;


Step 2: Load the OCSPd Configuration Utility with the following command:

```
# /opt/ocspd/sbin/ocspd-config
```

Step 3: In the main menu, select '**OCSPd**':




Step 4: In the OCSPd menu, select '**RADIUS**':




Step 5: Specify the following Radius configuration settings and validate:



'CHAP' and 'PAP' protocols are supported by OCSPd.



Step 6: The OCSPd configuration is updated:




Configuring the LDAP Server

Step 1: Access the server through SSH with an account with administrative privileges;


Step 2: Load the OCSPd Configuration Utility with the following command:

```
# /opt/ocspd/sbin/ocspd-config
```

Step 3: In the main menu, select 'OCSPd':



Step 4: In the OCSPd menu, select 'RADIUS':



Step 5: Specify the following LDAP configuration settings and validate:



By default the LDAP configuration will use port 389 and SSL/TLS 'false'.



The filter settings is optional.

LDAP Settings

Configure LDAP Settings:

Host	:	[LDAP Server IP or DNS Name]
Port	:	[LDAP Port]
SSL/TLS	:	[LDAPS enabled?]
Bind DN	:	[LDAP Bind DN]
Bind Password	:	[LDAP Bind Password]
Base DN	:	[LDAP Base DN]
Filter	:	[LDAP Filter]
User Attribute:	:	[LDAP User Attribute]

<Accepter> **<Annuler >**

Step 6: The OCSPd configuration is updated:

OCSPd Configuration Modified

Please restart the OCSPd service

< OK >


Generating a new OCSPd Application Secret

Step 1: Access the server through SSH with an account with administrative privileges;


Step 2: Load the OCSPd Configuration Utility with the following command:

```
# /opt/ocspd/sbin/ocspd-config
```


Step 3: In the main menu, select '**OCSPd**':




Step 4: In the OCSPd menu, select '**SECRET**':



Step 5: Validate the new OCSPPd Application Secret:



Step 6: The OCSPPd configuration is updated:



Installing the OCSPd license

Step 1: Upload the 'ocspd.lic' file through SCP under '/tmp/ocspd.lic':

Step 2: Access the server through SSH with an account with administrative privileges;

Step 3: Move the license file and set the permissions using the following commands:

```
# mv /tmp/ocspd.lic /opt/ocspd/etc
# chown ocspd:ocspd /opt/ocspd/etc/ocspd.lic
# chmod 640 /opt/ocspd/etc/ocspd.lic
```

1.4.1. Configuring NGINX


Issuing a Certificate Request (PKCS#10)

Step 1: Access the server through SSH with an account with administrative privileges;

Step 2: Load the OCSPd Configuration Utility with the following command:

```
# /opt/ocspd/sbin/ocspd-config
```


Step 3: In the main menu, select '**NGINX**':



Step 4: In the NGINX menu, select 'CSR':



Step 5: Specify the DNS Name of the OCSPd server:



Step 6: The certificate request is generated and available under `/etc/nginx/ssl/ocspd.csr.new`:




Step 7: Sign the certificate request using the corporate PKI.


Installing a Server Certificate

Step 1: Upload the generated server certificate on the OCSPd server under `/tmp/ocspd.pem` through SCP;


Step 2: In the NGINX configuration menu, select 'CRT':



Step 3: Specify the path `'/tmp/ocspd.pem'` and validate:




Step 4: The server certificate is successfully installed:




Installing the Server Certificate Trust Chain

Step 1: Upload the server certificate trust chain (the concatenation of the Certificate Authority certificates in PEM format) on the OCSPd server under *'/tmp/server.bundle'* through SCP;


Step 2: In the NGINX configuration menu, select 'TS':



Step 3: Specify the path *'/tmp/server.bundle'* and validate:



Step 4: The server bundle is successfully installed:



1.4.2. Configuring the Firewall

EL6

Step 1: Access the server through SSH with an account with administrative privileges;

Step 2: Open ports TCP/80 and TCP/443 on the local firewall with the following commands:

```
# iptables -I INPUT 1 -p tcp -m tcp --dport 443 -j ACCEPT
```

```
# iptables -I INPUT 1 -p tcp -m tcp --dport 80 -j ACCEPT
```

Step 3: Save the local firewall configurations with the following command:

```
# /etc/init.d/iptables save
```

EL7

Step 1: Access the server through SSH with an account with administrative privileges;

Step 2: Open ports TCP/80 and TCP/443 on the local firewall with the following commands:

```
# firewall-cmd --zone=public --permanent --add-service=http  
# firewall-cmd --zone=public --permanent --add-service=https
```

1.5. Running as container

OCSPd is also packaged as a container, and can be run on container runtimes such as Docker or Kubernetes CRI-compliant runtimes.

Database considerations

OCSPd uses an embedded database to store application configuration. The database is created automatically when OCSPd is started for the first time. The database is stored in the `/ocspd/database` directory and needs to be persisted :

- On Docker, this can be done through a Docker volume or a bind mount.
- On Kubernetes, this can be done through a persistent volume claim.

Docker example

The bare minimum requirements to start an OCSPd instance is to pass through environment variables at least :

- a valid license through the `LICENSE` variable
- an application secret through the `APPLICATION_SECRET` variable

To do so, just run the following command :

```
docker run -p 9000:9000 -e LICENSE=$(cat ./ocspd.lic) -e  
APPLICATION_SECRET=QA3BgXqapXaEzLbX -v ./database:/ocspd/database:rw  
registry.evertrust.io/ocspd:3.1.3
```

The OCSPd server will be available at `http://localhost:9000`. To configure the instance, please refer to

the configuration section.

Configuration

The Docker image is configured through environment variables. The following environment variables are available :

General configuration

Variable	Type	Description	Default
LICENSE	string	A valid OCSPd license string, base64-encoded. Can be used if <code>LICENSE_PATH</code> is empty.	
LICENSE_PATH	path	Path where an OCSPd license file is mounted inside the container. Can be used if the license is not passed directly through <code>LICENSE</code> .	
APPLICATION_SECRET	string	Application secret used by OCSPd	



Your license usually contains newline characters, that you must replace by '\n' when setting it through the environment.

Configuring HTTPS

In production, it is strongly recommended to ensure all requests go through a layer of encryption. Configuring TLS for OCSPd will allow your reverse proxy to request OCSPd data using TLS.



If all settings are left empty, OCSPd will generate a self-signed certificate upon startup and still expose its HTTPS endpoint on

Variable	Type	Description	Default
HTTP_PORT	port	Port of the HTTP server	9000
HTTPS_PORT	port	Port of the HTTPS server	9443
HTTPS_KEYSTORE_PATH	string	Location where the keystore containing a server certificate is located.	

Variable	Type	Description	Default
HTTPS_KEYSTORE_PASSWORD	string	Password for the given keystore, if required by the keystore type	
HTTPS_KEYSTORE_TYPE	string	Format in which the keystore is. Can be either <code>pkcs12</code> , <code>jks</code> or <code>pem</code> (a base64-encoded DER certificate)	<code>pkcs12</code>
HTTPS_KEYSTORE_ALGORITHM	string	The key store algorithm	Platform default algorithm

Mailer configuration

Variable	Type	Description	Default
SMTP_HOST	string	SMTP host	
SMTP_PORT	port	SMTP port	
SMTP_SSL	boolean	Whether SSL should be used	
SMTP_TLS	boolean	Whether TLS should be used	
SMTP_USER	string	SMTP user	
SMTP_PASSWORD	string	SMTP password	

Radius configuration

Variable	Type	Description	Default
RADIUS_HOST	string	Radius host	
RADIUS_SECRET	string	Radius secret	
RADIUS_PORT	port	Radius port	
RADIUS_PROTOCOL	string	Radius protocol, <code>PAP</code> or <code>CHAP</code>	<code>PAP</code>

LDAP configuration

Variable	Type	Description	Default
LDAP_HOST	string	LDAP host	
RADIUS_SECRET	string	Radius secret	
LDAP_PORT	port	LDAP port	

Variable	Type	Description	Default
LDAP_SSL	boolean	Whether SSL should be used for LDAP	
LDAP_BIND_DN	string	Bind DN used to authenticate to LDAP	
LDAP_BIND_PASSWORD	string	Bind password used to authenticate to LDAP	
LDAP_BASE_DN	string	LDAP base DN	
LDAP_USERNAME_ATTRIBUTE	string	LDAP username attribute	

1.6. Initial OCSPd Access

Starting the OCSPd services

Step 1: Access the server through SSH with an account with administrative privileges;

Step 2: Start the ocspd service with the following command:

```
# /etc/init.d/ocspd start
```

Step 3: Start the nginx service with the following command:

```
# /etc/init.d/nginx start
```

Accessing the OCSPd Web Management Console

Step 1: Launch a web browser;

Step 2: Browse to '[https://\[IP or DNS Name of the OCSPd component\]](https://[IP or DNS Name of the OCSPd component])':



Welcome to EverTrust OCSP Management Console

A rounded rectangular input field with a light gray border. On the left side, there is a small gray icon of a person's head and shoulders, followed by the text 'Username' in a gray font.A rounded rectangular input field with a light gray border. On the left side, there is a small gray icon of a padlock, followed by the text 'Password' in a gray font.

Reset password

Login



The default administration credentials are:

- Login: **'administrator'**
- Password: **'ocspd'**

Step 3: Specify the default administration credentials and hit the **'Login'** button:

Configuration

- Certification Authorities
- CRL Cache
- Signers
- Hardware Security Modules

Permissions

- Administrators
- Roles

System

- Backup
- Restore
- Logs
- HTTP Proxies

Welcome administrator,

OCSP Healthcheck

OK

CRL Cache

0

Valid: 0 Expired: 0 Error: 0

Signers

0

Active: 0 Inactive: 0
Will expire in less than 30 days: 0

Faulty HSM

0

HTTP Proxies

0



It is **highly recommended** to create a dedicated administration account and delete the default one, or at least modify the default administrator password.

1.7. Uninstallation Procedure



Prior to uninstalling, please ensure that you have a **proper backup of the OCSPd component**. Once uninstalled, all the OCSPd data will be **irremediably lost!**

Uninstalling OCSPd consists in uninstalling:



- The OCSPd service;
- The NGINX service.

Uninstalling OCSPd

Step 1: Access the server through SSH with an account with administrative privileges;

Step 2: Uninstall OCSPd with the following commands:

```
# /etc/init.d/ocspd stop
# yum remove ocspd
# rm -rf /opt/ocspd
# rm -rf /var/log/ocspd
# rm -f /etc/default/ocspd
```

Uninstalling NGINX

Step 1: Access the server through SSH with an account with administrative privileges;

Step 2: Uninstall NGINX with the following commands:

```
# /etc/init.d/nginx stop
# yum remove nginx
# rm -rf /etc/nginx
# rm -rf /var/log/nginx
```

2. Admin guide

2.1. Introduction

Description

OCSPd (OCSP daemon) is an OCSP responder compliant with the following RFCs:

- RFC 6960
- RFC 5019

This project is powered up by:

- Akka
- BouncyCastle
- EHCache
- H2 Database
- IAIK PKCS#11 Wrapper
- Kamon
- Play! Framework
- Scala
- NGINX

This document is specific to OCSPd version **3.1.3**.

Scope

This document is an Administration Guide and details how to:

- Manage NGINX specific configuration (authentication, OCSP stapling);
- Manage Permissions (Administrators and Roles);
- Manage Hardware Security Modules (HSM);
- Manage Certificate Authorities;
- Manage OCSP Signers;

- Perform Backup and Restore operations;
- Monitor the service;
- Obtain Key Performance Indicators (KPI);
- Consume the OCSP service;
- Troubleshooting.

Out of Scope


This document does not detail how to install the OCSPd component. For installation and uninstallation procedures, please refer to the '**OCSPd Installation Guide**'.

2.2. NGINX Specific Configurations

OCSPd uses the NGINX web server to:

- Act as a proxy for the OCSPd Play! application (Web Management Console & OCSP responder);
- Serve the CRLs when the OCSPd component is used as an HTTP CRL Distribution Point.

The following schema summarizes the interaction between NGINX, the filesystem and the OCSPd Play! Application:



The NGINX configuration is defined in the file '*/opt/ocspd/etc/ocspd-httpd.conf*' and loaded through a symbolic link under '*/etc/nginx/conf.d/*'. Tweaking this configuration is possible, but any modification not specifically documented in this guide is **not supported**.

The NGINX configuration file can be tweaked to enable OCSP stapling.

Enabling OCSP Stapling



OCSPd can be natively used to perform OCSP Stapling. This section simply details how to activate OCSP Stapling on the OCSPd NGINX instance for the Web Management Console. This configuration is optional.



More information regarding OCSP Stapling can be found here [OCSP Stapling](#).



To enable OCSP Stapling, OCSPd must be able to process OCSP request regarding the Certificate Authority used to issue the server certificate.

Step 1: Access the server through SSH with an account with administrative privileges;

Step 2: Edit the file `'opt/ocspd/etc/ocspd-httpd.conf''`;

Step 3: Uncomment the following lines:

```
ssl_stapling on;
ssl_stapling_verify on;
ssl_stapling_responder http://127.0.0.1:9000/ocsp;
```

Step 4: Reload the NGINX configuration with the following command:

```
# /etc/init.d/nginx reload
```

Renewing the Server certificate


Issuing a Certificate Request (PKCS#10)

Step 1: Access the server through SSH with an account with administrative privileges;

Step 2: Load the OCSPd Configuration Utility with the following command:

```
# /opt/ocspd/sbin/ocspd-config
```


Step 3: In the main menu, select 'NGINX':



Step 4: In the NGINX menu, select 'CSR':



Step 5: Specify the DNS Name of the OCSPd server:



Step 6: The new certificate request is generated and available under `'/etc/nginx/ssl/ocspd.csr.new'`:




Step 7: Sign the certificate request using the corporate PKI.


Installing a Server Certificate

Step 1: Upload the generated server certificate on the OCSPd server under `'/tmp/ocspd.pem'` through SCP;


Step 2: In the NGINX configuration menu, select 'CRT':



Step 3: Specify the path `'/tmp/ocspd.pem'` and validate:



Step 4: The server certificate is successfully installed:



Step 5: Exit the configuration utility and reload the NGINX service with the following command:

```
# /etc/init.d/nginx reload
```

2.3. Initial Management Console Access and Logout

Management Console Access

Step 1: Access the Web Management Console using a Web browser *https://[IP or DNS Name of the OCSPd component]*;



Default credentials are:

- Login: **administrator**
- Password: **ocspd**

Step 2: Provide the default credentials and hit the 'Login' button:



Welcome to EverTrust OCSP Management Console

A rounded rectangular input field with a light gray border. On the left side, there is a small gray icon of a person's head and shoulders. The text 'Username' is positioned to the right of the icon.A rounded rectangular input field with a light gray border. On the left side, there is a small gray icon of a padlock. The text 'Password' is positioned to the right of the icon.

[Reset password](#)

[Login](#)

Step 3: The Web Management Console is displayed:

Configuration

- Certification Authorities
- CRL Cache
- Signers
- Hardware Security Modules


Permissions

- Administrators
- Roles

System

- Backup
- Restore
- Logs
- HTTP Proxies

Welcome administrator,



It is highly recommended to either:

- Modify the default administrator password
- Or Create a new administrator account and delete the default administrator one (to perform this operation, you need to create the new administrator account with the default administrator account, logout, login with the new administrator account and delete the default one).

Management Console Logout

Logout when logged in with Password (Local, Radius or LDAP)

Step 1: Hit 'Logout' in the header:



Profile About English ▼ Logout

Step 2: The Administrator is successfully logged out:

Success
Bye administrator!

OCSP

Welcome to EverTrust OCSP Management Console

[Reset password](#)

Logout when logged in with Certificate



The 'Logout' is not available when logged in with Certificate. Simply close the Web Browser.

2.4. Administrator Profile

Account Information

Step 1: Hit 'Profile' in the header to access to the profile page:



[Profile](#) [About](#) [English](#) ▾ [Logout](#)

Step 2: Administrator's account information that is logged in is displayed:

You'll find below your account information:

Username

administrator

Email

administrator@evertrust.fr

Certificate DN

Authentication Type

Password

You are not member of any role.

You own the following permissions:

Manage

Audit

System

Local Password *



Confirm Local Password *



Change Password

The following elements are displayed:

- **'Username'**: the currently logged in Administrator username;
- **'Email'**: the currently logged in Administrator email;
- **'Certificate DN'** (*if specified*): the currently logged in Administrator certificate DN;
- **'Authentication Type'**: the currently logged in Administrator authentication type;
- The complete list of roles that the currently logged in Administrator is member of;

- The detailed list of all permissions the currently logged in Administrator owns (it aggregates all permissions assigned personally and all permissions inherited from the Role(s) of which Administrator is member of). You have to mouseover each permission category to view the details.

Resetting Password



- When an administrator account is created, the associated password is not defined during the creation process and must be set afterward if password-based authentication must be configured for the administrator;
- Local Password can be changed if only the '**Authentication Type**' of the Administrator account has been set to '**Password**'.



The password must be compliant with the Password Policy defined.



An administrator can authenticate using a password even if a certificate DN was provided.

Step 1: Hit 'Profile' in the header to access to the profile page:



Profile About English ▼ Logout

Step 4: Specify the Administrator password (double input) and hit the '**Change Password**' button:



Change Password

Step 5: The Administrator password is set / reset:



Success

'administrator's local password has been successfully set



2.5. Managing Administrators

2.5.1. Creating an Administrator



When an administrator is created, the associated password is not set. Setting the password is mandatory to be able to consume the administrator account with password authentication.




Administrators can be declared:

- Manually;
- By providing a certificate.

Creating an Administrator Manually

Step 1: Access the OCSPd Web Management Console;

Step 2: In the '**Permissions**' left menu, select '**Administrators**':



Step 3: In the Administrators page, hit the '+' button at the bottom right of the table:



Step 4: Specify the following elements and hit the '**Add**' button:

- '**Username**': this is the username used to login on the Web Management Console;
- '**Email**': email of the administrator. For now, this field is not used, but in an upcoming version, it will be used to allow password reset;
- '**Certificate DN**' (*optional*): this allow to map the administrator account to a certificate DN when

performing certificate-based authentication;

- '**Authentication Type**': for now, OCSPd supports Password, Radius, LDAP and Certificate based authentication (X509);
- '**Roles**' (*optional and multiple select*): role(s) given to the administrator;
- '**Permissions**' (*click on each right to select it*): right(s) of manage/audit each module and perform system tasks given to the administrator.



Radius and LDAP authentication methods are available after configuring the dedicated servers on OCSPd. For more information about Radius and LDAP server's configuration, please refer to the '**OCSPd Installation Guide**'.



The issuing CA of the LDAP certificate has to be declared in the OCSPd if you want to use the LDAPS authentication.



'**Manage**' right is a '**read and modify**' right. '**Audit**' is a '**read-only**' right.

Username *
jjalvado

Email *
jja@evertrust.fr

Certificate DN 

Authentication Type *
Password

Roles

Please select the following rights you want to affect to the administrator:

- Manage Certification Authorities
- Audit Certification Authorities
- Manage Signers
- Audit Signers
- Manage HSMs
- Audit HSMs
- Manage Permissions
- Audit Permissions
- Backup
- Restore
- Logs Access
- Manage HTTP Proxies
- Audit HTTP Proxies

Cancel

Add

Step 5: The Administrator is successfully created:



Success
'jjalvado' successfully created



Administrators

Search 


Username	Email	Certificate DN	Authentication Type	Roles	
administrator	administrator@evertrust.fr	-	Password	-	 
jjalvado	jj@evertrust.fr	-	Password	-	 

Records per page: 10  |< < 1/1 > >| 

Creating an Administrator using a Certificate

Step 1: Access the OCSPd Web Management Console;

Step 2: In the 'Permissions' left menu, select 'Administrators':



Step 3: In the Administrators page, hit the '+' button at the bottom of the page:



Step 4: In the popup, hit the  button:



Please select the following rights you want to affect to the administrator:

Manage Certification Authorities

Audit Certification Authorities

Manage Signers

Audit Signers

Manage HSMs

Audit HSMs

Manage Permissions

Audit Permissions

Backup

Restore

Logs Access

Manage HTTP Proxies

Audit HTTP Proxies

Cancel

Add

Step 5: Specify the certificate to load (PEM or DER) and hit the 'Submit' button:

Please select the Administrator Certificate to upload (PEM or DER format)

Browse
jjalvado.pem  

Cancel

Submit

Step 6: The Administrator form is automatically populated with the following value:

- **'Username':** Common Name of the provided certificate;
- **'Email':** Extracted from the RFC822Name if defined in the certificate, empty otherwise;
- **'Certificate DN':** Distinguished Name of the provided certificate.

Specify the roles and permissions attributes (if required) and hit the '**Add**' button:

Username *
jjalvado

Email *
jja@evertrust.fr

Certificate DN
CN=Jean-Julien Alvado, OU=Users, O=EverTrust, C=FR  

Authentication Type *
X509 

Roles 

Please select the following rights you want to affect to the administrator:

- Manage Certification Authorities
- Audit Certification Authorities
- Manage Signers
- Audit Signers
- Manage HSMs
- Audit HSMs
- Manage Permissions
- Audit Permissions
- Backup
- Restore
- Logs Access
- Manage HTTP Proxies
- Audit HTTP Proxies

Cancel

Update

Step 6: The Administrator is successfully created:



Success
'jjalvado' successfully created



Administrators Search

Username	Email	Certificate DN	Authentication Type	Roles	
administrator	administrator@evertrust.fr	-	Password	-	
jjalvado	jjalvado@evertrust.fr	CN=Jean-Julien Alvado, OU=Users, O=EverTrust, C=FR	X509	-	

Records per page: 10 |< < 1/1 > >| +

2.5.2. Setting Administrator Password Policy

You can create your own password policy for administrators accounts on EverTrust OCSP.



The default password policy requires the use of a minimum 8-character password without any other criteria of complexity.

You can combine the following complexity criteria to create your own password policy:

Configuration file parameter	Signification
validation.length.min	Minimum length
validation.length.max	Maximum length
validation.lower.case.min	Minimum number of lowercase characters
validation.upper.case.min	Minimum number of uppercase characters
validation.digit.min	Minimum number of digits
validation.special.min	Minimum number of special characters

Step 1: Access the server through SSH with an account with administrative privileges;

Step 2: Modify the following configuration file `'/opt/ocspd/etc/ocspd.conf'` to set up your password policy:

```
authentication {
  password {
    [...]
    validation.length.min=
    validation.length.max=
```

```
validation.upper.case.min=  
validation.lower.case.min=  
validation.digit.min=  
validation.special.min=  
}
```

Step 3: Restart the OCSPd service with the following command:

```
# /etc/init.d/ocspd restart
```

2.5.3. Editing or deleting Administrators


Editing an Administrator



Any administrator's attribute can be modified, even the username one but the administrator attributes '**username**' and '**email**' must be unique.

Step 1: Access the OCSPd Web Management Console;

Step 2: In the '**Permissions**' left menu, select '**Administrators**':



Step 3: Click on the Administrator's name you are willing to edit or hit the  button:

jjalvado

jj@evertrust.fr

Password



Step 4: Modify the Administrator attributes and hit the '**Update**' button:

Username *
jjalvado

Email *
jja@evertrust.fr

Certificate DN 

Authentication Type *
Password

Roles

Please select the following rights you want to affect to the administrator:

- Manage Certification Authorities
- Audit Certification Authorities
- Manage Signers
- Audit Signers
- Manage HSMs
- Audit HSMs
- Manage Permissions
- Audit Permissions
- Backup
- Restore
- Logs Access
- Manage HTTP Proxies
- Audit HTTP Proxies

Cancel

Update

Step 5: The Administrator is successfully updated:



Success

'jjalvado' successfully updated




Deleting an Administrator



It is not possible to delete an Administrator account when logged in with this Administrator account.

Step 1: Access the OCSPd Web Management Console;

Step 2: In the 'Permissions' left menu, select 'Administrators':



Step 3: Hit the  button of the Administrator you are willing to delete:

jjalvado

jja@evertrust.fr

Password




Step 4: Hit the 'Confirm' button:

Do you really want to delete the administrator jjalvado?

Cancel

Confirm

Step 5: The Administrator is successfully deleted:



Success

'jjalvado' successfully deleted




2.6. Managing Roles

This section details how to manage OCSPd Roles.

Creating a Role

Step 1: Access the OCSPd Web Management Console;

Step 2: In the 'Permissions' left menu, select 'Roles':



Step 3: In the Roles page, hit the '+' button at the bottom of the page:



Step 4: Specify the following elements:

- '**Name**': name of the role;
- '**Description**' (*optional*): description of the role;
- '**Permissions**' (*click on each right to select it*): right(s) of manage/audit each module and perform system tasks given to the role.



'**Manage**' right is a '**read and modify**' right. '**Audit**' is a '**read-only**' right.

And hit the '**Add**' button:

Name *

Auditor

Description

Can audit all modules

Please click on the rights you want to affect to this role:

Manage Certification Authorities

✓ Audit Certification Authorities

Manage Signers

✓ Audit Signers

Manage HSMs

✓ Audit HSMs

Manage Permissions

✓ Audit Permissions

Backup

Restore

Logs Access

Manage HTTP Proxies

✓ Audit HTTP Proxies

Cancel

Add

Step 5: The Role is successfully created:



Success

'Auditor' successfully created



Role

Name	Description	Permissions	
------	-------------	-------------	--

Auditor	Can audit all modules	Audit System	  
---------	-----------------------	--	---


Records per page: 10 ▾ |< < 1/1 > >|



Editing a Role

Step 1: Access the OCSPd Web Management Console;

Step 2: In the 'Permissions' left menu, select 'Roles':



Step 3: Click on the Role's name you are willing to edit or hit the  button:

Auditor

Can audit all modules

Audit

System



Step 4: Modify the Role attributes and hit the 'Update' button:

Name *
Auditor

Description
Can audit all modules

Please click on the rights you want to affect to this role:

- | | |
|---|---|
| <input type="checkbox"/> Manage Certification Authorities | <input checked="" type="checkbox"/> Audit Certification Authorities |
| <input type="checkbox"/> Manage Signers | <input checked="" type="checkbox"/> Audit Signers |
| <input type="checkbox"/> Manage HSMs | <input checked="" type="checkbox"/> Audit HSMs |
| <input type="checkbox"/> Manage Permissions | <input checked="" type="checkbox"/> Audit Permissions |
| <input type="checkbox"/> Backup | |
| <input type="checkbox"/> Restore | |
| <input type="checkbox"/> Logs Access | |
| <input type="checkbox"/> Manage HTTP Proxies | <input checked="" type="checkbox"/> Audit HTTP Proxies |

Cancel

Update

Step 5: The Role is successfully updated:




Success
'Auditor' successfully updated



Display and manage Members of a Role

Step 1: Access the OCSPd Web Management Console;

Step 2: In the 'Permissions' left menu, select 'Roles':



Step 3: For the Role you want to see the Members, hit the  button:

Auditor

Can audit all modules

Audit

System



Step 4: Hit the button  to remove the Administrator from the Role:

Search



Username

Email

jjalvado

jjja@evertrust.fr



Records per page: 5  |< < 1 / 1 > >|

Step 5: The Administrator is successfully removed from the Role:



Success


'jjalvado' successfully removed from role 'Auditor'



Deleting a Role

Step 1: Access the OCSPd Web Management Console;

Step 2: In the 'Permissions' left menu, select 'Roles':



Step 3: Hit the  button of the Role you are willing to delete:

Auditor

Can audit all modules

Audit

System




Step 4: Hit the 'Confirm' button:

Do you really want to delete the role Auditor?

Cancel

Confirm

Step 5: The Role is successfully deleted:



Success

'Auditor' successfully deleted



2.7. Managing Hardware Security Modules

OCSPd supports **PKCS#11 compatible crypto devices** (Hardware Security Module, Smartcard, Token) to store the private key of the OCSP Signers.

Supported Hardware Security Modules

As of today, OCSPd has been successfully tested with the following Hardware Security Modules:

- SoftHSM v1 & v2;
- Bull Proteccio;
- Gemalto Safenet Protect Server;
- Gemalto Safenet Luna Network HSM;
- nCipher nShield Connect HSM;
- Utimaco SecurityServer.



If your HSM is not in the list above, this does not necessarily mean that it is not functional, just that it is not officially supported. Contact us and we will accommodate to have it supported.

2.7.1. Managing Modules

Registering a Module




Initializing the PKCS#11 module must be performed using the tools provided by the HSM provider.



Registering a PKCS#11 module consists in loading the associated PKCS#11 library.

Step 1: Access the OCSPd Web Management Console;

Step 2: In the '**Configuration**' left menu, select '**Hardware Security Modules**':



Step 3: In the HSM page, hit the '+' button at the bottom of the page:



Step 4: Specify:

- '**Name**': the name of the HSM module;
- '**Description**' (*optional*): a description of the HSM module;
- '**PKCS#11 Library**': the absolute path where the PKCS#11 library is available.

And hit the '**Register**' button:

Name *
SoftHSMv2

Description
Software HSM v2

Library *
/usr/local/opt/softhsm/lib/softhsm/libsofthsm2.so

Cancel Register

Step 5: The PKCS#11 module is registered:



Success

'SoftHSMv2' successfully registered



Hardware Security Module

SoftHSMv2 ●

Software HSM v2

/usr/local/opt/softhsm/lib/softhsm/libsofthsm2.so


  



Editing a Module

Step 1: Access the OCSPd Web Management Console;

Step 2: In the 'Configuration' left menu, select 'Hardware Security Modules':



Step 3: In the HSM page, hit the  button of the Module you are willing to edit:

SoftHSMv2 

Software HSM v2

/usr/local/opt/softhsm/lib/softhsm/libsofthsm2.so



Step 4: Modify the Module attributes and hit the 'Update' button:

Name *

SoftHSMv2

Description

Software HSM v2

Library *

/usr/local/opt/softhsm/lib/softhsm/libsofthsm2.so

Cancel

Update

Step 5: The Module is successfully updated:



Success

'SoftHSMv2' successfully updated




Unregistering a Module



A Module cannot be unregistered if a Slot is registered on the considered Module.

Step 1: Access the OCSPd Web Management Console;

Step 2: In the '**Configuration**' left menu, select '**Hardware Security Modules**':



Step 3: In the HSM page, hit the  button of the Module you are willing to unregister:

SoftHSMv2 ●

Software HSM v2

/usr/local/opt/softhsm/lib/softhsm/libsofthsm2.so




Step 4: Hit the '**Confirm**' button:

Do you really want to unregister the HSM SoftHSMv2? No cryptographic material will be deleted if you proceed.

Cancel

Confirm

Step 5: The module is unregistered:



2.7.2. Managing HSM slots


Registering a Slot



Slot are registered on a Module, i.e. you need to register a Module first prior to registering a Slot.

Step 1: Access the OCSPd Web Management Console;

Step 2: In the '**Configuration**' left menu, select '**Hardware Security Modules**':



Step 3: Hit the **+** button of the Module for which you are willing to register a Slot:

SoftHSMv2 ●

Software HSM v2

/usr/local/opt/softhsm/lib/softhsm/libsofthsm2.so



Step 4: Specify:

- '**Slot ID**' (*select*): ID of the Slot on the PKCS#11 Module;
- '**PIN**': the slot PIN;
- '**Worker(s)**': the number of concurrent sessions to open on the slot (limited to '5' by default, but this can be increased by tweaking the configuration).

And hit the '**Register**' button:

HSM Name
SoftHSMv2

Slot ID *
0x31c6937c

PIN *
●●●●

Worker(s) *
1

Cancel Register

Step 5: The Slot is successfully registered:

Success

'0x31c6937c' successfully registered

×

SoftHSMv2 ●

Software HSM v2

`/usr/local/opt/softhsm/lib/softhsm/libsofthsm2.so`


✎ + 🗑

Slot ID	FIPS 140-2 Level 3	Status	Worker(s)	
0x31c6937c	⊗	●	1	🔒 🔧 🗑

Modifying the Slot PIN

Step 1: Access the OCSPd Web Management Console;

Step 2: In the 'Configuration' left menu, select 'Hardware Security Modules':



Step 3: Hit the  button of the Slot for which you are willing to modify the PIN:

SoftHSMv2 

Software HSM v2

/usr/local/opt/softhsm/lib/softhsm/libsofthsm2.so



Slot ID	FIPS 140-2 Level 3	Status	Worker(s)	
0x31c6937c			1	  

Step 4: Specify the new Slot PIN and hit the 'Set' button:

PIN *
●●●●




Confirm PIN *
●●●●



Cancel

Set

Step 5: The Slot PIN is successfully set:



Success


'0x31c6937c' successfully updated



Modifying the Slot Worker(s)

Step 1: Access the OCSPd Web Management Console;

Step 2: In the 'Configuration' left menu, select 'Hardware Security Modules':



Step 3: Hit the  button of the Slot for which you are willing to modify the Worker(s):

SoftHSMv2 ●
Software HSM v2
`/usr/local/opt/softhsm/lib/softhsm/libsofthsm2.so`   

Slot ID	FIPS 140-2 Level 3	Status	Worker(s)	
0x31c6937c	<input type="checkbox"/>	●	1	  

Step 4: Specify the new 'Worker(s)' value and hit the 'Set' button:

Worker(s) *
5

Cancel

Set

Step 5: The Worker(s) is successfully set:



Success

'0x31c6937c' successfully updated




Unregistering a Slot



A Slot cannot be unregistered if it is referenced by a Signer, i.e. the Signer storing its private key within the considered Slot must be deleted first.

Step 1: Access the OCSPd Web Management Console;

Step 2: In the 'Configuration' left menu, select 'Hardware Security Modules':



Step 3: Hit the  button of the Slot you are willing to unregister:

SoftHSMv2 ●

Software HSM v2

/usr/local/opt/softhsm/lib/softhsm/libsofthsm2.so



Slot ID	FIPS 140-2 Level 3	Status	Worker(s)
0x31c6937c	<input type="checkbox"/>	●	1


Step 4: Hit the 'Confirm' button:

Do you really want to unregister the slot 0x31c6937c? No cryptographic material will be deleted if you proceed.

Cancel

Confirm

Step 5: The Slot is successfully unregistered:



2.7.3. Managing FIPS 140-2 Level 3 Key Generation Mode

Enabling FIPS 140-2 Level 3 Key Generation Mode




Enabling 'FIPS 140-2 Level 3 Key Generation Mode' causes key to be generated using the 'CKM_RSA_X9_31_KEY_PAIR_GEN' mechanism within the HSM. Do not enable this mode unless:

- The Hardware Security Module supports this key generation mechanism;
- Issuing the key pair using the key mechanism is mandatory.

Step 1: Access the OCSPd Web Management Console;

Step 2: In the '**Configuration**' left menu, select '**Hardware Security Modules**':



Step 3: Hit the button of the Slot for which you are willing to enable FIPS 140-2 Level 3 Key Generation Mode:

SoftHSMv2 ●


Software HSM v2

/usr/local/opt/softhsm/lib/softhsm/libsofthsm2.so



Slot ID	FIPS 140-2 Level 3	Status	Worker(s)	
0x31c6937c	<input checked="" type="checkbox"/>	●	1	

Step 4: FIPS 140-2 Level 3 is now enabled. New keypair will be generated using the 'CKM_RSA_X9_31_KEY_PAIR_GEN' mechanism:



Success

'0x31c6937c' successfully updated



SoftHSMv2 ●

Software HSM v2

/usr/local/opt/softhsm/lib/softhsm/libsofthsm2.so




Slot ID	FIPS 140-2 Level 3	Status	Worker(s)	
0x31c6937c		●	1	

Disabling FIPS 140-2 Level 3 Key Generation Mode

Step 1: Access the OCSPd Web Management Console;

Step 2: In the 'Configuration' left menu, select 'Hardware Security Modules':




Step 3: Hit the  button of the Slot for which you are willing to disable FIPS 140-2 Level 3 Key Generation Mode:

SoftHSMv2    
Software HSM v2
/usr/local/opt/softhsm/lib/softhsm/libsofthsm2.so

Slot ID	FIPS 140-2 Level 3	Status	Worker(s)
0x31c6937c			1   

Step 4: FIPS 140-2 Level 3 is now disabled. New keypair will be generated using the 'CKM_RSA_PKCS_KEY_PAIR_GEN' mechanism:



Success

'0x31c6937c' successfully updated



SoftHSMv2



Software HSM v2

/usr/local/opt/softhsm/lib/softhsm/libsofthsm2.so



Slot ID	FIPS 140-2 Level 3	Status	Worker(s)	
0x31c6937c	<input type="checkbox"/>	●	1	  

2.7.4. HSM specifics

nCipher nShield Connect

To integrate the nCipher nShield Connect HSM, the **cknfastrc** configuration file must be updated with the following configuration entry:

```
CKNFAST_FAKE_ACCELERATOR_LOGIN=Y
```

Utimaco CryptoServer

To integrate the Utimaco CryptoServer, the **ocspd** configuration file (**/etc/default/ocspd**) must be modified and the following lines must be added at the beginning of the configuration file:

```
# Utimaco specific export  
export CS_PKCS11_R2_CFG=[CS_PKCS11_R2]
```

Where [CS_PKCS11_R2] is the absolute path of the **cs_pkcs11_r2.cfg** configuration file.

The [CS_PKCS11_R2] configuration file must be updated as well to enable a session keep alive:


```
# Prevents expiring session after inactivity of 15 minutes  
KeepAlive = true
```

2.8. Managing Certificate Authorities

2.8.1. Importing a Certificate Authority

Step 1: Access the OCSPd Web Management Console;

Step 2: In the 'Configuration' left menu, select 'Certificate Authorities':



Step 3: In the Certificate Authorities page, hit the '+' button at the bottom of the page:



Step 4: Browse for the certificate of the Certificate Authority you are willing to load (PEM or DER) and hit the 'Submit' button:

Please select the CA certificate to register (PEM or DER format).

Browse
EverTrust_TCA.pem  

Cancel

Submit

Step 5: The Certificate Authority is loaded and the details of the CA are displayed:



Details



Conf



CRL

DN

CN=EverTrust Technical CA, O=EverTrust, C=FR

Issuer DN

CN=EverTrust Root CA, O=EverTrust, C=FR

Serial

0x5d0b9d09fdceb7ecb0abd669

Not Before

Mar 27, 2019 12:57 PM +01:00

Not After

Sep 20, 2038 01:57 PM +02:00

Cancel

Next

Step 6: Click on 'Next' and specify the following configuration information:

- '**Name**': This is the name of the Certificate Authority within OCSPd;
- '**Is compromised?**': If this parameter is checked, any OCSP request targeting this Certificate Authority will trigger a '**revoked**' response and the revocation date will be set as the request date;
- '**Trusted for Authentication?**': If this parameter is checked, this Certification Authority is trusted for client certificate authentication on the OCSPd Web Management Console;
- '**Enable OCSP?**': This parameter indicates if OCSPd should serve OCSP responses for this particular Certificate Authority;

- **'Outdated Revocation Status Policy'**: This defines the behavior of the OCSP responder when the revocation status is unavailable (CRL is expired or cannot be downloaded). OCSPd implements 3 policies:
 - **'Revoked'**: any OCSP request will trigger a **revoked** response (RFC 5019 compliant);
 - **'Unknown'**: any OCSP request will trigger an **unknown** response;
 - **'Last available status'**: the OCSP responder will determine the status based on the last information available (this policy is not compliant with the RFC 5019, but it allows avoiding denial of services when CRL is unavailable or expired);
- **'Default Signer'**: This parameter indicates which signer should be used to sign the OCSP responses for this particular CA when the responder to use is not defined in the URL.



CA Name *
EverTrust Technical CA

Is compromised?

Trusted for Authentication?

Enable OCSP?

Outdated Revocation Status Policy
Revoked

Default Signer

Back

Cancel

Next

Step 7: Click on 'Next' and specify the following CRL configuration information:

- '**CRL URL**': This is the URL where the CRL can be downloaded from. OCSPd currently supports **HTTP and LDAP only**;
- '**CRL Name**': This parameter specifies how the CRL should be named when available through HTTP on the OCSPd component. For example, if the CRL name is configured as '**acsa**', then, the CRL will be available under `http://[EverTrustOCSP IP or DNS NAME]/acsa.crl` (DER format) and `http://[EverTrustOCSP IP or DNS NAME]/acsa.pem` (PEM format). If the CRL Name parameter is not defined, the CRL will be name after the CA Name;
- '**Refresh Period**': This parameter defines the CRL refresh period in seconds. For example, for a value of 300, OCSPd will attempt to download the CRL every 300 seconds, i.e. 5 minutes. **If this parameter is set to '0', the CRL will not be downloaded at all**;
- '**Timeout**': This parameter defines the CRL timeout in milliseconds. **If this parameter is set to '0', no timeout will be set**;
- '**Proxy**': This parameter defines the proxy to use to download the CRL. Proxies are declared in the '**Proxies**' page;
- '**Notify on CRL expiration?**': If this parameter is checked, an email will be sent to the Administrator when the CRL is expired;
- '**CRL Expiration Prior Notice Delay (in seconds)**': This parameter defines the CRL expiration delay prior to notify the Administrator. For example, for a value of 43200, OCSPd will send an email to the Administrator 12 hours before the expiration of this Certification Authority CRL and each time the CRL is refreshed (defined by '**Refresh Period**' parameter);
- '**Notify on CRL error?**': If this parameter is checked, an email will be sent to the Administrator when the CRL retrieving of this Certification Authority will fail and each time the CRL is refreshed (defined by '**Refresh Period**' parameter).

Step 8: Hit the '**Import**' button:



Details



Conf



CRL

CRL URL

http://pki.evertrust.fr/tsa.crl

CRL Name

tca

Refresh Period (in seconds)

300



Timeout (in milliseconds)

60



HTTP Proxy



Notify on CRL Expiration?



CRL Expiration Prior Notice Delay (in seconds)

43200

Notify On CRL Error?



Back

Cancel

Import

Step 9: The Certificate Authority is successfully imported:



Success

'EverTrust Technical CA' successfully created



Certification Authority

Search


Name	DN	Default Signer	
EverTrust Technical CA	CN=EverTrust Technical CA, O=EverTrust, C=FR	-	

Records per page: 10 |< < 1/1 > >|

2.8.2. Editing a Certificate Authority

Step 1: Access the OCSPd Web Management Console;

Step 2: In the 'Configuration' left menu, select 'Certificate Authorities':



Step 3: Click on the Certificate Authority's name you are willing to edit or hit the button:

Step 4: Update all the Certificate Authority attributes and hit the 'Update' button:

Configuration

CRL

Details

CA Name *

EverTrust Technical CA

Is compromised?

Trusted for Authentication?

Enable OCSP?

Outdated Revocation Status Policy

Revoked

Default Signer

Cancel

Update

Step 5: The Certificate Authority is successfully updated:



Success

'EverTrust Technical CA' successfully updated



2.8.3. CRL management


Forcing a CRL Refresh



This option is available only if a 'CRL URL' has been set in the Certificate Authority configuration.

Step 1: Access the OCSPd Web Management Console;

Step 2: In the 'Configuration' left menu, select 'Certificate Authorities':




Step 3: Hit the  button of the Certificate Authority you are willing to refresh the CRL:

EverTrust Technical CA

CN=EverTrust Technical CA, O=EverTrust, C=FR



Step 4: The Certificate Authority CRL is successfully refreshed:



Success


'EverTrust Technical CA' CRL has been successfully refreshed



Uploading a CRL manually

Step 1: Access the OCSPd Web Management Console;

Step 2: In the 'Configuration' left menu, select 'Certificate Authorities':



Step 3: Hit the  button of the Certificate Authority you are willing to upload a CRL:

EverTrust Technical CA

CN=EverTrust Technical CA, O=EverTrust, C=FR



Step 4: Browse for the CRL (PEM or DER) and hit the 'Submit' button:


Please select the CRL to upload (PEM or DER format)

Browse
tsa.crl  

Cancel

Submit

Step 5: The CRL is successfully uploaded:



Success


CRL successfully uploaded for 'EverTrust Technical CA'



2.8.4. Downloading the CA certificate

Step 1: Access the OCSPd Web Management Console;

Step 2: In the '**Configuration**' left menu, select '**Certificate Authorities**':



Step 3: Hit the  button of the Certificate Authority you are willing to download the certificate (in PEM format):

EverTrust Technical CA

CN=EverTrust Technical CA, O=EverTrust, C=FR




Step 4: The Certificate Authority's certificate is downloaded in PEM format.

2.8.5. Deleting a Certificate Authority

Step 1: Access the OCSPd Web Management Console;

Step 2: In the 'Configuration' left menu, select 'Certificate Authorities':



Step 3: Hit the  button of the Certificate Authority you are willing to delete:

EverTrust Technical CA

CN=EverTrust Technical CA, O=EverTrust, C=FR




Step 4: Hit the 'Confirm' button:

Do you really want to delete the CA EverTrust Technical CA?

Cancel

Confirm

Step 5: The Certificate Authority is successfully deleted:




Success

'EverTrust Technical CA' successfully deleted



2.8.6. Understanding the Cache Management

When CRL are downloaded, they are cached using an in-memory caching system (EHCache). The status of the cache is available in the '**CRL Cache**' entry of the '**Configuration**' left menu:



Basically, when a new CRL is downloaded or uploaded, the CRL is parsed and each revocation entry is inserted / updated in the cache. Addressing the cache being faster than querying the CRL object, it results in a great performance enhancement, particularly for big CRL.

The cache status details for each Certificate Authority:

- The Certificate Authority Name ('**CA Name**');
- The last time of cache refresh for the CRL ('**Cache - Last Refresh**');
- The number of revoked entries in the cache for the considered Certificate Authority ('**CRL - Size**');
- The current cache status for the considered Certificate Authority: 'Valid', 'Warning', 'Expired', 'Error' ('**Status**').
- The following CRL info are available when mouseover the 🔍 button:
 - The issuance date of the last downloaded CRL for the considered Certificate Authority;
 - The expiration date of the last downloaded CRL for the considered Certificate Authority.
 - The CRL serial number of the last downloaded CRL for the considered Certificate Authority.



CA Name	Cache - Last Refresh	CRL - Size	Status
EverTrust Technical CA	Nov 18, 2020 05:34 PM +01:00	457	●

Records per page: 10 |< < 1/1 > >| 



You can retrieve information about the cache 'error' or 'warning' by hovering on the '**Status**'.

The cache status can be refreshed by hitting the '**Refresh**' button:



Success

All CRLs have been successfully refreshed



The cache cannot be purged. To purge the cache, restart the OCSPd service.




The number of cache entries in the cache does not reflect the number of entries in the CRL. Expired entries will be removed from the CRL, but not from the cache. Therefore, the cache contains at least as many entries as in the CRL, but can contain more. It contains all the revoked entries parsed in the different CRL since the OCSPd service was started.

2.9. Managing OCSP Signers

2.9.1. Creating a Signer

Step 1: Access the OCSPd Web Management Console;

Step 2: In the '**Configuration**' left menu, select '**Signers**':



Step 3: In the Signers page, hit the '+' button at the bottom of the page:



Step 4: Specify:

- '**Name**': the name of the Signer;
- '**KeyStore**': the keystore for the Signer Private Key. It can be:
 - '**Software**': the private key is stored in the OCSPd database;
 - '**Hardware**': the private key is stored in any defined HSM Slot;
- '**Key Parameter**': the type and size of the keypair (RSA and ECDSA are supported);
- '**DN**': the Distinguished Name of the Signer certificate.

And hit the '**Add**' button:

Name *
EverTrust Technical CA Signer

Keystore *
Software

Key Parameter *
RSA / 2048

DN *
CN = EverTrust Technical CA Signer

Response Signing Algorithm *
SHA1

Responder ID Type *
Distinguish Name

Worker(s) *
5

Notify On Signer Expiration?


Signer Expiration Prior Notice Delay (in days)
15

Cancel **Add**



The other attributes are irrelevant until the Signer certificate is issued and installed.

Step 5: The Signer is successfully created:



Success

'EverTrust Technical CA Signer' successfully created



Signer Search

Name	DN	Not After	Keystore	Key	Algorithm	Status	
EverTrust Technical CA Signer	CN = EverTrust Technical CA Signer	-	Software	RSA / 2048	sha1	i	✎ ↓ ↕ 🗑️


Records per page: 10 |< < 1/1 > >| +

2.9.2. Managing Signer Certificate Requests

Editing a Signer prior Certificate Request

Step 1: Access the OCSPd Web Management Console;

Step 2: In the 'Configuration' left menu, select 'Signers':



Step 3: Click on the Signer's name you are willing to edit or hit the  button:

EverTrust Technical
CA Signer

CN = EverTrust
Technical CA Signer

Software

RSA / 2048

sha1



Step 4: Modify the Signer Distinguish Name and hit the 'Update' button:

Name *
EverTrust Technical CA Signer

Keystore *
Software

Key Parameter *
RSA / 2048

DN *
CN = EverTrust Technical CA Signer 

Response Signing Algorithm *
SHA1

Responder ID Type *
Distinguish Name

Worker(s) *
5


Notify On Signer Expiration?

Signer Expiration Prior Notice Delay (in days)
15

Cancel

Update

Step 5: The Signer is successfully updated:



Success


'EverTrust Technical CA Signer' successfully updated



Generating a Signer Certificate Request

Step 1: Access the OCSPd Web Management Console;

Step 2: In the 'Configuration' left menu, select 'Signers':



Step 3: Hit the  button of the Signer you are willing to generate a Certificate Request (PKCS#10):



Step 4: The PKCS#10 certificate is generated.




The request needs to be signed using your corporate PKI.


Installing a Signer Certificate

Step 1: Access the OCSPd Web Management Console;

Step 2: In the 'Configuration' left menu, select 'Signers':



Step 3: Hit the  button of the Signer you are willing to install the certificate for:



Step 4: Browse for the Signer certificate (PEM or DER) and hit the 'Submit' button:

Please select the Signer Certificate to upload (PEM or DER format)

Browse
EverTrust_Technical_CA_Signer.pem  

Cancel

Submit

Step 5: The Signer certificate is successfully installed:

 **Success** ✕
'EverTrust Technical CA Signer' successfully updated

Signer Search 

Name	DN	Not After	Keystore	Key	Algorithm	Status
EverTrust Technical CA Signer	CN=EverTrust Technical CA Signer, OU=OCSP, O=EverTrust, C=FR	Nov 18, 2022 06:00 PM +01:00	Software	RSA / 2048	sha1	    

Records per page: 10   1/1  




2.9.3. Managing Signers

Editing a Signer

Step 1: Access the OCSPd Web Management Console;

Step 2: In the '**Configuration**' left menu, select '**Signers**':



Step 3: Select the Signer you are willing to edit or hit the  button:

Signer Search 

Name	DN	Not After	Keystore	Key	Algorithm	Status	
EverTrust Technical CA Signer	CN=EverTrust Technical CA Signer, OU=OCSP, O=EverTrust, C=FR	Nov 18, 2022 06:00 PM +01:00	Software	RSA / 2048	sha1	<input checked="" type="checkbox"/>	   

Records per page: 10 |< < 1/1 > >| +

Step 4: Modify the following attributes:

- **'Response Signing Algorithm'**: this attribute defines the signing algorithm used by the signer to sign the OCSP responses (SHA1, SHA2 and SHA3 hash algorithms are supported);
- **'Responder ID Type'**: this attribute defines the format of the Responder ID included in the OCSP response (Certificate ID or Certificate DN);
- **'Worker(s)'**: the number of concurrent signing for the signer (by default, the maximum number of workers is set to 5 but this can be tweaked in the configuration);
- **'Notify on signer expiration'**: if this attribute is checked, an email will be sent to the

Administrator when the certificate of this Signer is expired. This notification is sent daily at 00:00;

- '**Signer Expiration Prior Notice Delay (in days)**': this attribute defines how many days before this signer certificate expires an email should be sent to the administrator.

And hit the '**Update**' button:

Signer Settings

Signer Certificate Details

Name *

EverTrust Technical CA Signer

Keystore *

Software

Key Parameter *

RSA / 2048

DN *

CN=EverTrust Technical CA Signer, OU=OCSP, O=EverTrust, C=FR



Response Signing Algorithm *

SHA1

Responder ID Type *

Distinguish Name

Worker(s) *

5

Notify On Signer Expiration?



Signer Expiration Prior Notice Delay (in days)

15

Cancel

Update



Signer's certificate information is available under the tab named 'Signer Certificate Details':

DN

CN=EverTrust Technical CA Signer, OU=OCSP, O=EverTrust, C=FR

Issuer DN

CN=EverTrust Technical CA, O=EverTrust, C=FR

Serial

0xd0ba88a163ddcbbd23bfa9bf

Not Before

Nov 18, 2020 05:55 PM +01:00


Not After

Nov 18, 2022 06:00 PM +01:00

Cancel

Update

Step 5: The Signer is successfully updated:



Success

'EverTrust Technical CA Signer' successfully updated




Deleting a Signer



A Signer cannot be deleted if it is enabled. You **MUST** disable it prior to be able to delete it.

Step 1: Access the OCSPd Web Management Console;

Step 2: In the '**Configuration**' left menu, select '**Signers**':



Step 3: Hit the  button of the Signer you are willing to delete:

Signer Search 

Name	DN	Not After	Keystore	Key	Algorithm	Status	
EverTrust Technical CA Signer	CN=EverTrust Technical CA Signer, OU=OCSP, O=EverTrust, C=FR	Nov 18, 2022 06:00 PM +01:00	Software	RSA / 2048	sha1	<input type="checkbox"/>	   

Records per page: 10 < > 1/1 >| 

Step 4: Hit the 'Confirm' button:

Do you really want to delete the signer EverTrust Technical CA Signer?

Cancel

Confirm


Step 5: The Signer is successfully deleted:




2.9.4. Downloading a Signer Certificate

Step 1: Access the OCSPd Web Management Console;

Step 2: In the 'Configuration' left menu, select 'Signers':



Step 3: Hit the  button of the Signer you are willing to download the certificate:



Name	DN	Not After	Keystore	Key	Algorithm	Status
EverTrust Technical CA Signer	CN=EverTrust Technical CA Signer, OU=OCSP, O=EverTrust, C=FR	Nov 18, 2022 06:00 PM +01:00	Software	RSA / 2048	sha1	<input type="checkbox"/>

Step 4: The Signer certificate is downloaded in **PEM format**.

2.9.5. Enabling or Disabling Signers


Enabling a Signer



A signer cannot be consumed until it is enabled.

Step 1: Access the OCSPd Web Management Console;

Step 2: In the '**Configuration**' left menu, select '**Signers**':



Step 3: Hit the  button of the Signer you are willing to enable:

Name	DN	Not After	Keystore	Key	Algorithm	Status	
EverTrust Technical CA Signer	CN=EverTrust Technical CA Signer, OU=OCSP, O=EverTrust, C=FR	Nov 18, 2022 06:00 PM +01:00	Software	RSA / 2048	sha1	<input checked="" type="checkbox"/>	   

Records per page: 10 |< < 1/1 > >| 

Step 4: The Signer is successfully enabled:



Signer

Search 

Name	DN	Not After	Keystore	Key	Algorithm	Status	
EverTrust Technical CA Signer	CN=EverTrust Technical CA Signer, OU=OCSP, O=EverTrust, C=FR	Nov 18, 2022 06:00 PM +01:00	Software	RSA / 2048	sha1		   

Records per page: 10  |< < 1/1 > >| 



The Signer can now be set as a default Signer in the Certificate Authority configurations.


Disabling a Signer



A Signer cannot be disabled if it is defined as a Default Signer in a Certificate Authority. You **MUST** modify this configuration prior to be able to disable it.

Step 1: Access the OCSPd Web Management Console;

Step 2: In the 'Configuration' left menu, select 'Signers':




Step 3: Hit the  button of the Signer you are willing to disable:

Signer							Search	Q		
Name	DN	Not After	Keystore	Key	Algorithm	Status				
EverTrust Technical CA Signer	CN=EverTrust Technical CA Signer, OU=OCSP, O=EverTrust, C=FR	Nov 18, 2022 06:00 PM +01:00	Software	RSA / 2048	sha1					

Records per page: 10 |< < 1/1 > >| 

Step 4: The Signer is successfully disabled:



Success

'EverTrust Technical CA Signer' successfully updated



Name	DN	Not After	Keystore	Key	Algorithm	Status	
EverTrust Technical CA Signer	CN=EverTrust Technical CA Signer, OU=OCSP, O=EverTrust, C=FR	Nov 18, 2022 06:00 PM +01:00	Software	RSA / 2048	sha1	<input type="checkbox"/>	   

Records per page: 10 < > 1/1 > >

2.10. Managing Services

Starting the OCSPd services

Step 1: Access the server through SSH with an account with administrative privileges;

Step 2: Start the ocspd service with the following command:

```
# /etc/init.d/ocspd start
```

Step 3: Start the nginx service with the following command:

```
# /etc/init.d/nginx start
```

Stopping the OCSPd services

Step 1: Access the server through SSH with an account with administrative privileges;

Step 2: Stop the ocspd service with the following command:

```
# /etc/init.d/ocspd stop
```

Step 3: Stop the nginx service with the following command:

```
# /etc/init.d/nginx stop
```

2.11. Backup and Restore

Backup




The following backup procedure does not detail how to back up the Hardware Security Module. Please refer to the HSM provider documentation and **ensure to perform an HSM backup** when using an hardware keystore.



A backup should be performed after each OCSPd configuration modification.

Step 1: Access the OCSPd Web Management Console;

Step 2: In the 'System' left menu, select '**Backup**':



Step 3: Click on '**Generate**' to retrieve a JSON backup file. Keep this file in a safe place.

Click on the following button to generate a JSON backup of the OCSP.




Restore



The following restore procedure does not detail how to restore the content of an HSM. Please refer to the HSM provider documentation for restoring HSM secrets.

Step 1: Access the OCSPd Web Management Console;

Step 2: In the 'System' left menu, select 'Restore':




Step 3: Browse for the OCSPd backup JSON file you want to restore and hit the 'Restore' button:

Browse to your OCSP backup file (JSON) and click on 'Restore' to restore OCSP configuration

Browse
ocspd-backup-1605718223883.json ✕

Restore

Step 5: The Backup is successfully restored:



Success
Backup successfully restored



2.12. Logs & Monitoring

Logs location

Logs are located under `/opt/ocspd/var/log` with the following distinction:

- Application logs are spooled to `'ocspd.log'`;
- Administration logs are spooled to `'ocspd-admin.log'` and the log file can be signed upon rotation.




These log files are rotated daily.

Logs download from the Web Management Console

Step 1: Access the OCSPd Web Management Console;

Step 2: In the **'System'** left menu, select **'Logs'**:



Step 3: All the logs files under `'/opt/ocspd/var/log'` can be downloaded:

Logs Search

File Name	File Size	Last Modified
tsa.crl	18.5KB	Nov 18, 2020 05:40 PM +01:00
tsa.pem	25.0KB	Nov 18, 2020 05:40 PM +01:00

Records per page: 10 |< < 1/1 > >| 

Step 3: All the logs files can be refreshed by hitting the '**Refresh**' button:





Success

All log files have been successfully refreshed



Managing the OCSPd Log Level

3 Log Levels are available within OCSPd:




- **'DEBUG'**: this mode is very verbose and provides debug information. It should not be turned on in production except for debugging purpose;
- **'INFO'**: this is the default mode. It provides error information along with OCSP request information;
- **'ERROR'**: this mode only logs errors.

Step 1: Access the server through SSH with an account with administrative privileges;


Step 2: Load the OCSPd Configuration Utility with the following command:

```
# /opt/ocspd/sbin/ocspd-config
```


Step 3: In the main menu, select '**OCSPd**':




Step 4: In the OCSPD menu, select '**OCSP_LOGLEVEL**':



Step 5: Select the Log Level and validate:



Step 6: The OCSPd configuration is updated:



Step 7: Exit the OCSPd Configuration Utility and restart the OCSPd service with the following command:

```
# /etc/init.d/ocspd restart
```

Monitoring

As of now, OCSPd does not offer any specific monitoring capability. Monitoring must be performed directly by the monitoring system.

Here are the elements to monitor:

- CRL Download through HTTP under '/';
- OCSP request through HTTP under '/ocsp';
- Administration interface through HTTPS.

2.13. HTTP Proxies

This section details how to manage OCSPd HTTP Proxies.




An HTTP Proxy can be bind to a Certification Authority when the CRL must be downloaded through a proxy.

Creating an HTTP Proxy

Step 1: Access the OCSPd Web Management Console;

Step 2: In the '**System**' left menu, select '**Proxies**':



Step 3: In the HTTP Proxies page, hit the '+' button at the bottom of the page:



Step 4: Specify the following elements:

- **'Name':** name of the proxy;
- **'Host':** host of the proxy (can be DNS name or IP address);
- **'Port':** port of the proxy.

And hit the **'Add'** button:


Name *
Proxy

Host *
proxy.evertrust.fr

Port *
8080

Cancel **Add**

Step 5: The HTTP Proxy is successfully created:



HTTP Proxy Search


Name	Host	Port	
Proxy	proxy.evertrust.fr	8080	

Records per page: 10 |< < 1/1 > >|

Editing an HTTP Proxy

Step 1: Access the OCSPd Web Management Console;

Step 2: In the 'System' left menu, select 'Proxies':



Step 3: Click on the HTTP Proxy's name you are willing to edit or hit the  button:

Proxy

proxy.evertrust.fr

8080



Step 4: Modify the HTTP Proxy attributes and hit the 'Update' button:

Name *

Proxy

Host *

proxy.evertrust.fr


Port *

8080

Cancel

Update

Step 5: The HTTP Proxy is successfully updated:



Success


'Proxy' successfully updated



Deleting an HTTP Proxy

Step 1: Access the OCSPd Web Management Console;

Step 2: In the 'System' left menu, select 'Proxies':



Step 3: Hit the  button of the HTTP Proxy you are willing to delete:

Proxy

proxy.evertrust.fr

8080




Step 4: Hit the 'Confirm' button:

Do you really want to delete the HTTP proxy Proxy?

Cancel

Confirm

Step 5: The HTTP Proxy is successfully deleted:



Success

'Proxy' successfully deleted



2.14. Key Performance Indicator(s)

OCSPd is able to send syslog event upon OCSP request. It allows to generate performance metrics within tools such as ELK or Splunk.




The following KPI configuration procedure does not detail how to aggregate metrics logs. Please refer to the **OCSPd KPI Integration Guide** documentation for more information.

Step 1: Access the server through SSH with an account with administrative privileges;


Step 2: Load the OCSPd Configuration Utility with the following command:

```
# /opt/ocspd/sbin/ocspd-config
```


Step 3: In the main menu, select '**OCSPd**':




Step 4: In the OCSPD menu, select '**METRICS**':



Step 5: Select the 'INFO' level to enable Syslog Metrics and validate:



Step 6: The OCSPd configuration is updated:



Step 7: Exit the OCSPd Configuration Utility and restart the OCSPd service with the following command:

```
# /etc/init.d/ocspd restart
```

Step 8: Create an '**ocspd.conf**' syslog configuration file in '**/etc/rsyslog.d**' with the following content to retrieve syslog events from OCSPd and store them into '**/var/log/ocspd/metrics.log**':

```
local6.* /var/log/ocspd/metrics.log
```



You can store syslog events wherever you want, '**/var/log/ocspd/metrics.log**' is the standard path in UNIX environment.

Step 9: Uncomment the following lines in the '**/etc/rsyslog.conf**':

```
$ModLoad imudp  
$UDPServerRun 514
```

Step 10: Restart the Rsyslog service with the following command:

```
# systemctl start rsyslog
```

2.15. Consuming the OCSP service

OCSPd is compliant with RFC:

- 6960
- 5019

Therefore, OCSP request can be realized through:

- HTTP GET (required for OCSP Stapling);
- HTTP POST (standard OCSP request).

When performing an OCSP request against OCSPd, the signer used to sign the response can be:

- Determine dynamically from the OCSP request (POST /ocsp or GET /ocsp/**ocsprequest**);
- Passed in the querystring of the URL (POST /signer/:signer_name/ocsp or GET /signer/:signer_name/ocsp/**ocsprequest**);
- Retrieve from the Certificate Authority settings thanks to the Certificate Authority's name passed in the querystring of the URL (POST /ca/:ca_name/ocsp or GET /ca/:ca_name_ocsp/**ocsprequest**).

The signer_name and ca_name have to be URL encoded. The ocsprequest is the base64 encoded OCSP request.



If the OCSP request contains several entries for several Certificate Authorities, the name of the signer must be passed in the querystring.

3. ELK integration

3.1. Introduction

ELK Description

ELK is the acronym for three open source projects:

- **Elasticsearch**: a search and analytics engine;
- **Logstash**: a server-side data processing pipeline that ingests data from multiple sources simultaneously, transforms it, and then sends it to a "stash" like Elasticsearch;
- **Kibana**: a web application to visualize data with charts and graphs in Elasticsearch.

EverTrust built a powerful monitoring and investigation dashboard for an EverTrust OCSP infrastructure using the complete ELK stack.

This project is powered up by:

- Elastic

This document is specific to ELK version 7.6.

Scope

This document is an Administration Guide and details how to:

- Deploy and configure log agents on each EverTrust OCSP node;
- Configure the Logstash pipeline;
- Import and manage Kibana indexes, visualizations and dashboards;

Out of Scope

This document does not detail how to install the ELK stack.

3.2. ELK for EverTrust OCSP description

To get a complete overview of the health and activity of an EverTrust OCSP infrastructure, several components are used. Each of them has a specific role in the complete logs processing and is described below.

Logs agents

- Metricbeat to collect System logs. Metricbeat is an ELK agent to periodically collect metrics from the operating system and from services running on the EverTrust OCSP node;
- Filebeat to collect NGINX logs. Filebeat is an ELK agent to monitor the NGINX log files;
- Syslog to collect EverTrust OCSP events. EverTrust OCSP supports the Syslog standard to spool event regarding the application activity.

Logs collector, aggregator and transformer

- Logstash is used as a centralized point of logs collection from all inputs described above. Logstash is configured to receive and transform logs inputs.


Logs storage and indexation

- Elasticsearch is used as point of storage, indexation of logs received from Logstash. Elasticsearch stores all inputs from Logstash as JSON objects. It provides high capacity of research data.

Logs shaping and visualization

- Kibana is a frontend application that sits on top of ELK stack. Kibana provides search and data visualization capabilities for data indexed in Elasticsearch.

ELK for EverTrust OCSF Overview



Metricbeat and Filebeat are additional and optional components. They are used to provide a complete overview of an EverTrust OCSF infrastructure. The support, maintenance and evolution of this component is **not provided by EverTrust**.

3.3. Logs agents' configuration

Prerequisites

The following flows are required:

- 5044/TCP between each EverTrust OCSF node and the Logstash machine;
- 5000/UDP between each EverTrust OCSF node and the Logstash machine.



All steps described below has to be performed on each EverTrust OCSF node you are willing to monitor.

Installation of the Elastic yum repository

Step 1: Access the EverTrust OCSF server through SSH with an account with administrative privileges;

Step 2: Download and install the Elastic public signing key using the following command:

```
# sudo rpm --import https://packages.elastic.co/GPG-KEY-elasticsearch
```

Step 3: Create a file with a **.repo** extension (for example, `elastic.repo`) in your `/etc/yum.repos.d/` directory and add the following lines:

```
[elastic-7.x]
name=Elastic repository for 7.x packages
baseurl=https://artifacts.elastic.co/packages/7.x/yum
gpgcheck=1
gpgkey=https://artifacts.elastic.co/GPG-KEY-elasticsearch
enabled=1
autorefresh=1
type=rpm-md
```

Metricbeat installation and configuration



Additional information about Metricbeat installation and operation is available [here](#).

Step 1: Access the EverTrust OCSF server through SSH with an account with administrative privileges;

Step 2: Install the Metricbeat agent using the following command:

```
# yum install metricbeat
```

Step 3: Enable the automatic Metricbeat boot at system start using the following command:

```
# systemctl enable metricbeat
```

Step 4: Modify the configuration of Metricbeat in the following file `/etc/metricbeat/metricbeat.yml` to send logs to 5044/TCP port of Logstash instead of Elasticsearch:

```
[...]
#output.elasticsearch:
  # Array of hosts to connect to.
  #hosts: [""]
[...]
output.logstash:
  # The Logstash hosts
  hosts: ["LOGTASH_HOSTNAME:5044"]
```

Step 5: Start the Metricbeat configuration with the following command:

```
# /etc/init.d/metricbeat start
```



Metricbeat configuration file is an YAML file. It is indentation sensitive.

Filebeat installation and configuration



Additional information about Filebeat installation and operation is available [here](#).

Step 1: Access the EverTrust OCSP server through SSH with an account with administrative privileges;

Step 2: Install the Filebeat agent using the following command:

```
# yum install filebeat
```

Step 3: Enable the automatic Filebeat boot at system start using the following command:

```
# systemctl enable filebeat
```

Step 4: Modify the configuration of Filebeat in the following file `'/etc/filebeat/filebeat.yml'` to setup NGINX logs directory:

```
filebeat.inputs:
[...]
```

- type: log

Change to true to enable this input configuration.

```
enabled: true
```

Paths that should be crawled and fetched. Glob based paths.

```
paths:
  - /var/log/nginx/http-access.log
exclude_files: ['\.gz$']
fields:
  log_source: nginx
```

Step 5: Modify the configuration of Filebeat in the following file `'/etc/filebeat/filebeat.yml'` to send logs to 5044/TCP port to Logstash instead of Elasticsearch:

```
[...]
```

```
#output.elasticsearch:
  # Array of hosts to connect to.
  #hosts: [""]
```

```
[...]
```

```
output.logstash:
  # The Logstash hosts
  hosts: ["LOGTASH_HOSTNAME:5044"]
```

Step 6: Start the Filebeat configuration with the following command:

```
# /etc/init.d/filebeat start
```



Filebeat configuration file is an YAML file. It is indentation sensitive.

Syslog configuration



Please refer to Key '**Performance Indicator(s)**' part of the '**EverTrust OCSP Installation Guide**'.

Step 1: Access the EverTrust OCSP server through SSH with an account with administrative privileges;

Step 2: Modify the '**ocspd.conf**' syslog configuration file in '**/etc/rsyslog.d**' with the following content to send syslog events to 5000/UPD port of Logstash:

```
local6.* @LOGTASH_HOSTNAME:5000
```

Step 3: Restart the Rsyslog service with the following command:

```
# systemctl start rsyslog
```

3.4. Logstash configuration

Prerequisites

Ensure that the following plugins are installed and enabled:

- **logstash-filter-json;**
- **logstash-filter-dns.**



All steps described below has to be performed on each EverTrust OCSP node you want to monitor.

Configuration

Step 1: Retrieve the '**ocspd-dictionary.yml**' on the Web Management Console of one of your EverTrust OCSP;

Step 2: Upload the '**ocspd-dictionary.yml**' file under '**/usr/share/logstash/config/**' on the Logstash server;

Step 3: Upload the '**ocspd-pipeline.yml**' file on the Logstash server;

Step 4: Modify the following lines of the '**ocspd-pipeline.yml**' file to specify the Elasticsearch host(s) and the authentication information:

```
elasticsearch {  
    hosts => ["ELASTICSEARCH_HOST:ELASTICSEARCH_PORT"]  
    user => "ELASTICSEARCH_USER"  
    password => "ELASTICSEARCH_PASSWORD"  
}
```

Step 4: Modify your current Logstash configuration to use the new '**ocspd-pipeline.yml**';

Step 5: Restart the Logstash service with the following command:

```
# systemctl restart logstash
```

3.5. Kibana configuration

Step 1: Access to the Kibana GUI using a web browser;



Welcome to Kibana

Your window into the Elastic Stack


Username

Password


Log in

Step 2: Login with an administrator;

Step 3: Navigate to 'Management' > 'Kibana' > 'Saved Objects';



Step 4: Click on 'Import' and select the 'ocspd.ndjson' file;



Step 5: Restart the kibana linux service on the machine;

3.6. Index details



JSON array are represented in the following table with the '.' delimiter.

NGINX index details

will find attached an example of an 'nginx-ocspd.json' log as stored by Elasticsearch in JSON format.

Here is the explanation of this JSON file.

JSON Entry	Signification
_source.ocspd.hostname	Hostname of OCSP node where the log is from
_source.ocspd.clientname	Hostname of the Client that did the request
_source.ocspd.logtype	Type of log
_source.clienip	Requester client @IP

JSON Entry	Signification
_source.ident	HTTP remote identity
_source.auth	HTTP remote user
_source.timestamp	Request timestamp
_source.verb	HTTP method
_source.request	URL of the request
_source.httpversion	HTTP version
_source.rawrequest	Complete request received
_source.response	HTTP status code
_source.bytes	Body bytes sent
_source.user_agent	User agent of the HTTP requester
_source.referrer	Address of the webpage which is linked to the resource being requested
_source.agent	Information about the Filebeat agent that send the log
_source.log	Log file name where this log is from

EverTrust OCSP index details

Inside an OCSP request, 3 situations can be found:

- Request for the status of a unique certificate for a unique Certificate Authority;
- Request for the status of multiples certificates for a unique Certificate Authority.
- Request for the status of multiples certificates for multiples Certificate Authorities.

That's why we have decided to split the EverTrust OCSP logs into two different log indexes. The first one gives information about the global OCSP request and is called '**request-ocspd**'. The second one gives details of each certificate status checked inside the request and is called '**item-ocspd**'.

EverTrust OCSP request

You will find attached an example of an '**request-ocspd.json**' log as stored by Elasticsearch in JSON format.

Here is the explanation of this JSON file.

JSON Entry	Signification
_source.ocspd.hostname	Hostname of OCSP node where the log is from
_source.ocspd.clientname	Hostname of the Client that did the request
_source.ocspd.logid	Identifier of log

JSON Entry	Signification
_source.ocspd.logtype	Type of log
_source.ocspd.request.status	Response status of the associated request
_source.ocspd.request.error	Response error of the associated request

EverTrust OCSP item

You will find attached an example of an **'item-ocspd.json'** log as stored by Elasticsearch in JSON format.

Here is the explanation of this JSON file.

JSON Entry	Signification
_source.ocspd.hostname	Hostname of OCSP node where the log is from
_source.ocspd.clientname	Hostname of the Client that did the request
_source.ocspd.logid	Identifier of log
_source.ocspd.logtype	Type of log
_source.ocspd.CAissuer.keyhash	Key hash of the CA issuer
_source.ocspd.CAissuer.name	Name of the CA issuer
_source.ocspd.cert.info	Information about the certificate (Certificate Serial Number/CA Issuer Name)
_source.ocspd.cert.status	Status of the certificate