



# Stream

Version 2.1, 2025-06-20

# Table of Contents

1. Installation	1
1.1. Introduction	1
1.2. Installing on CentOS/RHEL	1
1.3. Installing on Kubernetes	54
1.4. Monitoring	61
1.5. Troubleshooting	63
1.6. Advanced configuration	67
2. Admin guide	80
2.1. Introduction	81
2.2. Managing Certification Authorities	81
2.3. Managing Certificate Revocation	86
2.4. Managing Certificate Templates & EKUs	94
2.5. Managing Certificate Lifecycle	96
2.6. OpenSSH	97
2.7. Managing Keystores & Keys	101
2.8. Managing Notifications	105
2.9. Managing Security	109
2.10. Managing Stream instance	117
2.11. Timestamping	126
2.12. Backup and Restore	127
2.13. Dictionaries	130
2.14. Computation rule	133
2.15. Template Strings	141
3. Release notes	142
3.1. Stream 2.1.1 release notes	142
3.2. Stream 2.1.0 release notes	143

# 1. Installation

## 1.1. Introduction

### Description

Stream version 2.1 is EverTrust Certification Authority. This document is an installation procedure detailing how to install and bootstrap a Stream instance on your infrastructure for the version 2.1. It does not describe how to configure and operate the instance. Please refer to the administration guide for administration related tasks.

### Prerequisites

#### Choose an installation method

We offer two installation modes:

- A package-based installation on a server running **CentOS/RHEL 7.x/8.x/9.x x64**
- A cloud-native installation using Kubernetes

Depending on your needs, you'll have to choose the solution that fits your use cases the best. Reach out to our support team to get suggestions on how to deploy on your infrastructure.

#### Gathering your credentials

Both methods require that you download the binaries of the Stream software from our [software repository](#). The access to this repository is protected by username and password, which you should have got from our tech team. If you don't, you won't be able to continue with the installation. Email us to get your credentials, and come back to this step.

## 1.2. Installing on CentOS/RHEL

### 1.2.1. Pre-requisites

This section describes the system and software pre-requisites to install Stream.

#### System pre-requisites

The following elements are considered as system pre-requisites:

- A server running a **en-US** minimal install EL [7.x-8.x-9.x] x64 (RHEL / AlmaLinux / RockyLinux / Oracle Linux) with the network configured.
- Base EL [7.x-8.x-9.x] x64 repositories activated;
- An access with administrative privileges (root) to the server mentioned above as most commands are system-related and require super user privilege;

## Software pre-requisites

All the following packages can be necessary to deploy Stream. Most are available on public repositories but some require specific configurations.

Package name	Mandatory	Online Instructions	Offline instructions	Additional information
stream-2.1.x-1.x86_64.rpm	<input checked="" type="checkbox"/>	Online steps	Offline steps	
mongodb-mongosh, mongod-org-server-mongodb-org-tools, mongodb-database-tools`, mongodb-org-database-tools-extra	<input checked="" type="checkbox"/>	Online steps	Offline steps	
nginx		Online steps	N/A	Recommended reverse proxy
stream-hardening-1.x86_64.rpm		Online steps	Offline steps	Configuration hardening rpm

### 1.2.2. Installation

#### Installing MongoDB



Stream requires at least MongoDB version 4.4.2. For support reasons, EVERTRUST recommends to use the latest available version, which is MongoDB 6 at the time of writing.

Stream relies on MongoDB to store its data, whether it be configuration elements or certificate data. The necessary packages are `mongodb-org-server`, `mongodb-mongosh`, `mongodb-org-tools`, `mongodb-database-tools` and `mongodb-org-database-tools-extra`. To install and configure MongoDB on a Redhat-based OS, follow these steps using an account with administrative privileges:

#### Installation with Internet Access

These steps are for when the server has internet access

1. Follow step 1 of the official MongoDB installation tutorial.
2. Run the following command to install the RPMs:

```
# yum install -y mongodb-org-server mongodb-mongosh mongodb-org-tools mongodb-org-database-tools-extra mongodb-database-tools
```

#### Installation without Internet Access

1. Download the .rpm files directly from the MongoDB repository. Downloads are organized by Red Hat / CentOS version (e.g. 7 - do not select the Server folders), then MongoDB release version (e.g.

6.0), then architecture (e.g. x86\_64). Upload the files to the server.

2. Run the following command to install the RPMs:

```
# yum localinstall mongodb-org-server-x.y.z.arch.rpm mongodb-mongosh-x.y.z.arch.rpm
mongodb-org-tools-x.y.z.arch.rpm mongodb-org-database-tools-extra-x.y.z.arch.rpm
mongodb-database-tools-x.y.z.arch.rpm
```

## Common installation steps

3. Enable the service at startup with the following command:

```
# systemctl enable mongod
```

4. Start the `mongod` service with the following command:

```
# systemctl start mongod
```

5. Start the `mongosh` executable using the following command to check that the database is up and running:

```
# mongosh
```

For now, since we did not set up access control, everyone using `localhost` as DB URI can connect as administrator, which is something that needs to be prevented before setting up Stream.



The following section is not mandatory to get Stream up and running, but is highly recommended for security purposes.

6. In the mongo shell that was just opened, run the following commands:

```
> use admin;
> db.createUser(
  {
    user: "stream_db_admin",
    pwd: "AComplexPassword",
    roles: [ { role: "dbOwner", db: "stream" } ]
  }
)
```

This way, the created `stream_db_admin` user has owner permissions on the database named `stream`. You can change the `stream_db_admin` value to what you want to use as database username, the password to be what you want to use as a database password to match your password policies and the database name (the value to the `db` key) to what you want to use as the stream database. For the

password, you can also `passwordPrompt()` (without quotes) as the password value, which will prompt you for a password upon pressing Enter. Be careful though as this is a password prompt without confirmation.



If you plan on using special characters in the password, be careful as the MongoDB engine has trouble with some of them. For more information on this topic, please refer to the MongoDB documentation.

7. Edit the `/etc/mongod.conf` file and add the following section at the end:

```
security:
  authorization: enabled

setParameter:
  enableLocalhostAuthBypass: false
```

These options will prevent anonymous login to the MongoDB instance and will disable the localhost bypass.

8. Restart the MongoDB daemon to make the changes effective:

```
# systemctl restart mongod
```

9. When setting up Stream, use this connection string as the MongoDB URI :

```
mongodb://stream_db_admin:AComplexPassword@127.0.0.1:27017/stream?authSource=admin
```

If you used another username for the MongoDB user, replace the `stream_db_admin` part with the username that you used. Replace the `AComplexPassword` in the URI by the password that you chose when creating the account.

Replace `/stream` in the URI by `/databaseName` if you chose to use another name for your Stream database when creating the user.

## Installing NGINX



In order to install Stream, the server must have access to a repository (mirror, iso file, ...) of the linux distribution you are using in order to be able to install the dependencies of the software.

1. Connect to the server with an account with administrative privileges;
2. Install the NGINX web server using the following command:

```
# yum install nginx
```

3. Enable NGINX to start at boot using the following command:

```
# systemctl enable nginx
```

4. Stop the NGINX service with the following command:

```
# systemctl stop nginx
```

## Installing Stream

In order to install Stream, the server must have access to a repository (mirror, iso file, ...) of the linux distribution you are using in order to be able to install the dependencies of the software. Stream package has the following dependencies:



- `dialog`
- `java-17-openjdk-headless`
- `tzdata-java`

Please note that these packages may have their own dependencies.

## Installation from the EverTrust repository

Create a `/etc/yum.repos.d/stream.repo` file containing the EverTrust repository info:

```
[stream]
enabled=1
name=Stream Repository
baseurl=https://repo.evertrust.io/repository/stream-rpm/
gpgcheck=0
username=<username>
password=<password>
```

Replace `<username>` and `<password>` with the credentials you were provided.

You can then run the following to install the latest Stream version:

```
# yum install stream
```

To prevent unattended upgrades when running yum update, you should pin the Stream version by adding

```
exclude=stream
```

at the end of the `/etc/yum.repos.d/stream.repo` file after installing Stream.

## Installing from RPM

Download the latest RPM for version 2.1 on the Official EVERTRUST repository.

Upload the file '`stream-2.1.x-1.x86_64.rpm`' to the server;

Access the server with an account with administrative privileges;

Install the Stream package with the following command:

```
# yum localinstall /root/stream-2.1.x-1.x86_64.rpm
```

## Installing Tinkey



In order to install Tinkey, the server must have access to a repository (mirror, iso file, ...) of the linux distribution you are using in order to be able to install the dependencies of the software. Tinkey package has the following dependencies:

- `java-17-openjdk-headless`

Please note that these packages may have their own dependencies.

## Installation from the EverTrust repository

Create a `/etc/yum.repos.d/tinkey.repo` file containing the EverTrust repository info:

```
[tinkey]
enabled=1
name=Tinkey Repository
baseurl=https://repo.evertrust.io/repository/tinkey-rpm/
gpgcheck=0
username=<username>
password=<password>
```

Replace `<username>` and `<password>` with the credentials you were provided.

You can then run the following to install the latest Tinkey version:

```
# yum install tinkey
```

To prevent unattended upgrades when running `yum update`, you should pin the Tinkey version by adding

```
exclude=tinkey
```

at the end of the `/etc/yum.repos.d/tinkei.repo` file after installing Tinkey.

## Installing from RPM

Download the latest RPM for tinkey on the Official EVERTRUST repository.

Upload the file '`tinkey-<latest>.noarch.rpm`' to the server;

Access the server with an account with administrative privileges;

Install the Tinkey package with the following command:

```
# yum localinstall /root/tinkei-latest.noarch.rpm
```

## 1.2.3. Configuration

### Initial Configuration

#### Introduction

This section assumes that Stream is running in a confined environment: nobody but the person performing the configuration operation and the key ceremony stakeholders should have access to Stream yet, and they should do so under the supervision of a security officer.

Selinux should be disabled during the initial configuration and bootstrapping operations. It will be re-enabled following the security guidelines.

```
# setenforce Permissive
```

To ensure that it is permissive, run the following command

```
# getenforce
```

This should return `Permissive`

### Configuring the firewall

In order for Stream to work properly, the following ports are used:



- Exposed: 443 for HTTPS access to the product (through the web interface or through the API);
- Exposed: 80 for HTTP access to the product only to retrieve CRLs (the only allowed endpoint must be `/crls/*`, this is the case for the default NGINX configuration);
- Internal: 25520 and 7626 for high-availability configurations through the Pekko

framework.

- Internal: 9000 for the Stream API.

Connect to the server with an account with administrative privileges;

Open port TCP/443 on the local firewall with the following command:

```
# firewall-cmd --permanent --add-service=https
```

Stream also needs HTTP traffic allowed since it is required to set up the CRLDPs :

```
# firewall-cmd --permanent --add-service=http
```

To make the change effective, you need to restart the firewall service:

```
# systemctl restart firewalld
```

Enable the service at startup with the following command:

```
# systemctl enable firewalld
```

## Generating a Tink keyset

To protect its secrets, Stream relies on Tink. A Tink keyset can be issued as:

- A plaintext keyset (stored as a file, protected by the filesystem rights and SELinux);
- A GCP keyset (protected by a master key in a GCP KMS);
- An AWS keyset (protected by a master key in an AWS KMS).
- A PKCS#11 keyset (protected by a master key in an HSM).



In order to generate a keyset, the **Tinkey** tool must be installed.

Connect to the server with an account with administrative privileges;

Start the Stream configuration utility by running:

```
# /opt/stream/sbin/stream-config
```

In the main menu, select '**Stream**':



In the Stream menu, select '**STREAM\_TINK\_KEYSET**':



## Generating a plaintext keyset

In the Tink Keyset Generation menu, select '**PLAINTEXT**':




The keyset will be generated automatically. For the changes to take effect, you must restart the Stream service by running:

```
# systemctl restart stream
```

## Generating a GCP protected keyset

In the Tink Keyset Generation menu, select '**GCP**':



The URL of the GCP master key must be typed in the menu.

After pressing **OK**, the keyset will be generated automatically. For the changes to take effect, you must restart the Stream service by running:

```
# systemctl restart stream
```

## Generating an AWS protected keyset

In the Tink Keyset Generation menu, select '**AWS**':



The URL of the AWS master key must be typed in the menu.

After pressing **OK**, the keyset will be generated automatically. For the changes to take effect, you must restart the Stream service by running:

```
# systemctl restart stream
```

## Generating a PKCS#11 protected keyset

In the Tink Keyset Generation menu, select '**PKCS11**':

The URL of the PKCS#11 master key must be typed in the menu.

The expected format is:

```
pkcs11://object=<object name>;type=<object type>;slot-id=<slot id>?module-  
path=<library path>&pin-value=<pin>;
```

Example:

```
pkcs11://object=kek;type=secret-key;slot-id=-1?module-  
path=/usr/lib/softhsm/libsofthsm2.so&pin-value=1234";
```

After pressing **OK**, the keyset will be generated automatically. For the changes to take effect, you must restart the Stream service by running:

```
# systemctl restart stream
```


## Generating a Play secret

Connect to the server with an account with administrative privileges;

Start the Stream configuration utility by running:

```
# /opt/stream/sbin/stream-config
```

In the main menu, select '**Pekko\_Play**':



In the Pekko\_Play menu, select '**SECRET**':



Validate the new Stream Application Secret:



The Stream configuration is updated:



```
Stream Configuration Modified
Please restart the Stream service
< |K>
```

For the changes to take effect, you must restart the Stream service by running:

```
# systemctl restart stream
```

## JVM Configuration


Stream allows you to configure the *Xms* (minimum memory allocation pool) and *Xmx* (maximum memory allocation pool) parameters of the JVM running Stream using the configuration tool.

Connect to the server with an account with administrative privileges;


Start the Stream configuration utility by running:

```
# /opt/stream/sbin/stream-config
```


In the configuration menu, select **Stream**:



In the Stream configuration menu, Select **JVM**:



Specify the 2048 for *xms* and 3072 for *xmx* parameters and select 'OK':



The new JVM parameters are configured.

For the changes to take effect, you must restart the Stream service by running:

```
# systemctl restart stream
```


## MongoDB URI Configuration

Connect to the server with an account with administrative privileges;


Start the Stream configuration utility by running:

```
# /opt/stream/sbin/stream-config
```


In the main menu, select **Stream**:



In the Stream configuration menu, Select **MONGODB\_URI**:



Specify the MongoDB URI to target your MongoDB instance:



Stream is installed to target a local MongoDB instance by default.



If you use an external MongoDB (such as MongoDB Atlas Database or dedicated On-premises database) instance:

- Create a user with "read/write" permissions on your MongoDB instance;
- Create a replicaSet if using a MongoDB cluster;
- Specify a MongoDB URI that does match your context.

*External MongoDB database URI syntax*

```
mongodb+srv://<user>:<password>@<hostname>:<port>/stream
```

*External MongoDB cluster of databases URI syntax*

```
mongodb+srv://<user>:<password>@<hostname1>:<port1>,<hostname-2>:<port2>/stream?replicatSet=<replicaset>&authSource=admin
```

The MongoURI is configured.

For the changes to take effect, you must restart the Stream service by running:

```
# systemctl restart stream
```

## Stream Hostname Configuration

Connect to the server with an account with administrative privileges;

Start the Stream configuration utility by running:

```
# /opt/stream/sbin/stream-config
```


In the main menu, select **Stream**:



In the Stream configuration menu, Select **STREAM\_HOSTNAME**:



Specify the DNS FQDN by which Stream will be accessed:



The Stream Hostname is configured:



```
Stream Configuration Modified
Please restart the Stream service
< |K>
```

For the changes to take effect, you must restart the Stream service by running:

```
# systemctl restart stream
```

## Generating an event seal secret

Stream will generate functional events when using the software.


These events are typically signed and chained to ensure their integrity. Therefore, you must specify a sealing secret for this feature to work properly.

Connect to the server with an account with administrative privileges;


Start the Stream configuration utility by running:

```
# /opt/stream/sbin/stream-config
```


In the main menu, select '**Stream**':



In the Stream menu, select '**STREAM\_SEAL\_SECRET**':



Validate the new event seal secret:



The even seal secret is now configured:



```
Stream Configuration Modified
Please restart the Stream service
-----
< OK >
```

For the changes to take effect, you must restart the Stream service by running:

```
# systemctl restart stream
```

## Installing the Stream license



You should have been provided with a `stream.lic` file. This file is a license file and indicates an end of support date.


Upload the `stream.lic` file (using SCP or other means) under `/tmp/stream.lic`;

Connect to the server with an account with administrative privileges;


Start the Stream configuration utility by running:

```
# /opt/stream/sbin/stream-config
```


In the main menu, select **Stream**:




In the Stream configuration menu, Select **STREAM\_LICENSE**:



Specify the path `/tmp/stream.lic` and validate:



The Stream License is configured:



For the changes to take effect, you must restart the Stream service by running:

```
# systemctl restart stream
```

## Installing Stream on a cluster of servers



This section must not be followed if you plan on deploying Stream in standalone mode (vs cluster mode). WARNING: This section does not explain how to install Stream on a Kubernetes cluster. Please refer to the dedicated section.

In the main menu, select '**Pekko\_Play**':

```
-----EverTrust Stream Configuration Utility-----
+-----+
| SMTP      Configure SMTP relay
| Administrator Configure Stream Administrator's Email
| Akka_Play  Configure Akka and Play for EverTrust Stream
| Stream     Configure EverTrust Stream
| NGINX     Configure Local NGINX and External Front-End Support
| EXIT      Exit Configuration Utility
+-----+
| < OK >          <Cancel>
+-----+
```

In the Pekko\_Play menu, select '**PEKKO\_HA**':

```
-----Akka and Play Settings-----
+-----+
| SECRET    Generate Play Secret for Stream
| PLAY_LOGLEVEL Configure Play and ReactiveMongo Log Level
| AKKA_HA   Configure Akka and Stream High Availability (optional)
| EXIT      Exit Configuration
+-----+
| < OK >          <Cancel>
+-----+
```

In this menu, specify either the IP address or the DNS name for each server that will be running Stream on this cluster with pekko management port, as well as the local node index (the number of the node that you are configuring at that moment).



Note that the local node index must match the current node hostname or ip parameter:

```
-----HA: Akka Nodes Configuration for Stream-----
| Enter 2 or 3 Akka Nodes information if you want to setup High Availability.
| Leave empty otherwise.
+-----+
| IHA nodes in hostname:port format, comma separated:
| node1.stream.fr:8558,node2.stream.fr:8558,node3.stream.fr:8558
| Local Node Index (starts at 0):0
| Artery of the local node in hostname:port format:
| node1.stream.fr:25520
+-----+
| < OK > <Cancel>
```

Save your changes from the menu.


The High Availability mode is now configured on the current node:

```
-----Stream Configuration Modified-----
| WARNING: you modified the /etc/default/stream file.
| That file MUST be exactly the same on all the nodes, except for the
| AKKA_MANAGEMENT_LOCAL (Local Node Index) parameter.
| Once configuration has been adjusted on all nodes, please restart Stream.
+-----+
| < OK >
```


You must now configure your other nodes, but because they belong to the same cluster they need to share the **same pekko play secret, the same stream licence, the same stream seal secret, the same stream hostname, the same mongo database, the same x509 enforcing and the same stream tink keyset**. In order to be able to do that, you need to copy the configuration file that was generated by the stream-config app, named `/etc/default/stream` and paste it on each one of your nodes;

Then on each other node, run the Stream Configuration utility with the following command:

```
$ /opt/stream/sbin/stream-config
```



In the Pekko\_Play menu, select 'PEKKO\_HA':



Here, you need to change the local node index to match the hostname of the node that you are configuring:

```
-----HA: Akka Nodes Configuration for Stream-----
| Enter 2 or 3 Akka Nodes information if you want to setup High Availability.
| Leave empty otherwise.
+-----+
| HA nodes in hostname:port format, comma separated:
| node1.stream.fr:8558,node2.stream.fr:8558,node3.stream.fr:8558
| Local Node Index (starts at 0):1
| Artery of the local node in hostname:port format:
| node2.stream.fr:25520
+-----+
| < OK > <Cancel>
```



You will need to import the Stream licence file on each node manually, following the guidelines of section [Installing the Stream license](#).

Additionally, on each node, you will need to open the ports used for Pekko\_HA and Pekko\_MGMT, which are by default 25520 and 7626:

```
$ firewall-cmd --permanent --add-port=25520/tcp
$ firewall-cmd --permanent --add-port=7626/tcp
```

Reload the firewall configuration with:

```
$ systemctl restart firewalld
```

Restart the Stream service on each one of the nodes:

```
$ systemctl restart stream
```

## Bootstrapping EverTrust Stream


### Installing a bootstrap certificate

Connect to the server with an account with administrative privileges;


Start the Stream configuration utility by running:

```
# /opt/stream/sbin/stream-config
```

In the main menu, select 'NGINX':



In the NGINX menu, select '**BOOTSTRAP**':



Specify the DNS Name of the Stream server (the same that you used as Stream hostname previously):



The self-signed certificate is going to be generated and automatically installed for Nginx to use directly:



This certificate is meant to be used to bootstrap Stream and should be replaced as

quickly as possible as it is highly unsecured.

## Starting the services

Assuming that all prior configuration operations have been performed as documented in the installation guide and that a bootstrap certificate has been installed as explained in the previous section, the services must be started:

1. Connect to the server with an account with administrative privileges;
2. Start the stream service with the following command:

```
# systemctl start stream
```

3. Verify the NGINX configuration with the following command:

```
# nginx -t
```

4. Restart the NGINX service with the following command:

```
# systemctl restart nginx
```


## Retrieving initial password

For the first log-in, you must find the administrator password in the `/opt/stream/var/run/adminPassword` file.


The default administration login is `administrator`.

## Accessing the Stream Web Interface

1. Launch a web browser;
2. Browse to `https://[IP or DNS Name of the Stream component]/ui#`;
3. When prompted with a security issue, click on the button to accept the risks and proceed anyway. This alert is raised by the use of the self-signed certificate.



4. Specify the default administration credentials and hit the **Login** button:



It is **highly recommended** to delete the `adminPassword` file from your machine once you saved it somewhere safe.

## Initial Key Ceremony

Before deploying to production, the initial key ceremony should take place

### Configure a keystore

To protect the keys, keystores (cloud or physical) should be configured. Follow the Administration Guide steps in **Managing Keystores & Keys › Keystores in Stream** to configure your Keystore.

### Create keys

A key should be created for each Certification you wish to add. The keys can be generated externally, or using Stream.

Key creation steps depend on the type of keystore:

- **KMS:**  
KMS keys can be created using Stream following the Administration Guide steps in **Managing Keystores & Keys › Managing keys in Stream › Cloud KMS** or directly in the KMS following your KMS documentation.
- **Software Keystore:**  
Software keys can be created using Stream following the Administration Guide steps in **Managing Keystores & Keys › Managing keys in Stream › Software keystore**.
- **Hardware Security Module:**  
HSM keys can be created using Stream following the Administration Guide steps in **Managing**

**Keystores & Keys › Managing keys in Stream › PKCS#11 HSM.** Please note that extra steps may be required at HSM level depending on the model of HSM used.

Once the keys have been created, they should appear in the keystore on Stream after a refresh.

## Create your Certification Authorities

Once keys have been created the Certification Authorities can be created following the Administration Guide steps in **Managing Certification Authorities**.

## Finalizing Stream Configuration

### Configuring Stream default templates

If you intend to use Stream as your certification authority, default templates should be created.

As Stream is template-oriented, default templates will be used when enrolling certificates.

Two templates are considered as defaults:

- A `tlsClient` template for TLS client certificates
- A `tlsServer` template for TLS server certificates


To create these templates:

Connect to the server with an account with administrative privileges;


Start the Stream configuration utility by running:

```
# /opt/stream/sbin/stream-config
```

In the main menu, select '**Stream**':



In the Stream menu, select '**STREAM\_DEFAULT\_TEMPLATE**':



The templates are automatically created and available in **Certificates > Templates**.



**mongosh** must be installed and the mongo URI configured for this configuration to work

## Installing a Server Authentication Certificate


### Issuing a Certificate Request (PKCS#10)

Connect to the server with an account with administrative privileges;


Start the Stream configuration utility by running:

```
# /opt/stream/sbin/stream-config
```

In the main menu, select '**NGINX**':



In the NGINX menu, select '**CSR**':



Specify the DNS Name of the Stream server (the same that you used as Stream hostname previously):



The certificate request is generated and available under `'/etc/nginx/ssl/stream.csr.new'`:

```
New NGINX Server Certificate Request
The new request is available under "/etc/nginx/ssl/stream.csr.new"
< OK >
```

## Signing the certificate

The CSR generated at the previous steps must then be signed using an existing PKI. If you do not have an existing PKI, please refer to the [Key Ceremony Documentation](#) to create one.


## Sign using Stream



This step assumes that the Key Ceremony already happened, i.e the operational CAs are imported into Stream as managed CAs.

1. Access Stream's web administration console and log in using the default administration credentials that were obtained at [this section](#);
2. Browse to '**Certificates > Enroll**';
3. Fill in the following information:
  - CA to enroll on: Select the CA that is issuing the server certificates for your organization;
  - Template to enroll on: Select the certificate template that was created at [this step](#) that should be named 'tlsServer';
  - CSR type: Select 'File', then click the paper clip icon and import the CSR that was generated at [this step](#);

Then click 'Enroll':



You can retrieve the enrolled certificate in PEM format from the '**Certificates > Search**': download this certificate in PEM

## Sign using an external Certification Authority



The certificate must have the `serverAuthentication` Extended Key Usage

You will need to provide your certificate authority with the `/etc/nginx/ssl/stream.csr.new` file that was generated at the previous step.

## Installing the Server Certificate


Upload the signed server certificate (in PEM format) on the Stream server under `/tmp/stream.crt` (using SCP or other means);

Connect to the server with an account with administrative privileges;

Start the Stream configuration utility by running:

```
# /opt/stream/sbin/stream-config
```

In the NGINX configuration menu, select 'CRT':



Specify the path `/tmp/stream.crt` and validate:



The server certificate is successfully installed:



## Installing the Server Certificate Trust Chain



You must follow this section only if you signed the server certificate with an existing PKI. If you self-signed the server certificate, you do not need to follow this step.

Upload the server certificate trust chain (the concatenation of the Certificate Authority certificates in PEM format) on the Stream server under `/tmp/stream.bundle` (using SCP or other means);




The bundle should contain only the Certificate Authority certificates in PEM format and **NOT** the server certificate

Connect to the server with an account with administrative privileges;


Start the Stream configuration utility by running:

```
# /opt/stream/sbin/stream-config
```

In the NGINX configuration menu, select 'TC':



Specify the path `/tmp/stream.bundle` and validate:



The server bundle is successfully installed:

```
NGINX Configuration Modified
Server Trust Chain successfully imported!
Please restart the NGINX service
< |K >
```

Verify the NGINX configuration with the following command:

```
# nginx -t
```

Restart the NGINX service with the following command:

```
# systemctl restart nginx
```


## Configuring administrator certificate authentication

To authenticate as administrator on stream using a certificate, it is possible to either use a certificate generated on Stream, or to use an external certificate.


### Issuing a Certificate Request (PKCS#10)

#### Generating the CSR on Windows


1. Press 'Windows Key + R' then type 'certmgr.msc' and press enter;
2. Expand 'Personal' then double click 'Certificates';
3. In the top bar, click 'Action > All Tasks > Advanced Operations > Create custom requests':



4. On the 'Before You Begin' and the 'Select Certificate Enrollment Policy' screens, click 'Next';
5. In the 'Custom request' window, select 'CNG Key' in the template drop-down menu and 'PKCS#10' as the request format, then click 'Next':



6. In the 'Certificate Information' window, click 'Details' then 'Properties':




7. In the 'Certificate Properties' pop-up that opened:


- General tab: Leave everything as default
- Subject tab: In the subject name category enter the DN using the standard DN format then click Add:



It is recommended for a certificate DN to contain at least a CN, OU, O and C element




- Extensions tab: Leave everything as default
- Private Key tab: Expand 'Key options' and select '2048' for the key size, then expand 'Select Hash Algorithm' and select 'sha256' for the hash algorithm:



Click apply, then OK, then Next;

8. In the next window, select a place to save the CSR and select 'Base64' as File format, then click 'Finish':



## Generating the CSR on Linux/MacOS

1. Start a shell instance;
2. Run the following command, replacing the DN with your information:

```
$ openssl req -new -newkey rsa:2048 -subj "/CN=LASTNAME Firstname/C=FR/OU=.../"  
-keyout ./stream_admin.key -out ./stream_admin.csr
```

This command will prompt you for a password to encrypt the CSR private Key



It is recommended for a certificate DN to contain at least a CN, OU, O and C element

## Signing the certificate

### Using a Stream-signed certificate



This step assumes that the Key Ceremony already happened, i.e the operational CAs are imported into Stream as managed CAs.

1. Access Stream's web administration console and log in using the default administration credentials that were obtained at [this section](#);
2. Browse to '**Certificates > Enroll**';
3. Fill in the following information:
  - CA to enroll on: Select the CA that is issuing the user certificates for your organization. Note that it must have the 'Is trusted for client authentication' switch turned on in the interface;
  - Template to enroll on: Select the certificate template that was created at [this step](#) that should be named 'tlsClient';
  - CSR type: Select 'File', then click the paper clip icon and import the CSR that was generated at

this step;

Then click 'Enroll':

CA to enroll on  
UserAuthCA

Template to enroll on  
tisClient

CSR type:  File  Text (Copy-paste)

Import a CSR file  
stream\_admin.csr

Subject DN:  
CN=LASTNAME Firstname

No SAN and no extension

Key type:  
RSA / 2048

Cancel Enroll

You can retrieve the enrolled certificate in PEM format from the '**Certificates > Search**': download this certificate in PEM

## Using an external-signed certificate



The certificate must contain the clientAuthentication Extended Key Usage in order to be used as an authentication certificate on Stream

## Trusting the issuing CA for client authentication

In order for the client authentication certificate to work as intended, the issuing CA must be trusted for client authentication on Stream.

- If your certificate was signed by a Stream managed CA:  
Browse to **Certification Authorities > Managed CAs**, select your Issuing CA and toggle on '**Is trusted for client authentication**'
- If your certificate was signed by an external CA:  
If your CA is not yet imported, import it using the administration guide steps in **Managing Certification Authorities > Importing an External Certification Authority**.  
Browse to **Certification Authorities > External CAs**, select your Issuing CA and toggle on '**Is trusted for client authentication**'

## Creating the SuperAdmin role in Stream

At this point, you should be logged into the Stream web administration console with the default administrator account.

1. Go to **Security > Roles** and click  ;
2. Fill-in the following information:

- **Name:** SuperAdmin;
- **Description :** Super administrator role that has all rights on Stream. Use with caution;
- **Configuration permissions :** Click the '+' button then click on 'Section' and select 'All permissions of all type' and click the 'Add' button;
- **Lifecycle permissions :** Click the '+' button, then :
  - Click on 'CA' and select 'All';
  - Click on 'Template' and select 'All';
  - Click on 'Rights' and select 'All';
  - Click the 'Add' button.

3. Click the 'Save' button at the top of the page.

The SuperAdmin role is now created.

## Giving the SuperAdministrator role to the certificate

1. Access Stream's web administration console and log in using the default administration credentials that were obtained at this section;
2. Browse to 'Security > Authorizations' then click  and select 'Add authorization manually';
3. Import a certificate by clicking on certificate button ;
4. Once the identifier has been filled with the certificate DN click the 'Add' button;
4. Click the 'Add role' button and select the 'SuperAdmin' role previously created from the drop down menu;
5. Click the 'Save' button at the top of the page;

Now the PEM certificate has the SuperAdmin permission in Stream.

## Creating a PKCS#12 file from the private key and the PEM

This step can only be done using OpenSSL.

1. Connect to the server with an account with administrative privileges;
2. Upload the PEM of the certificate you used to create the SuperAdmin user at the previous step in the same folder where the private key that was used to generate the CSR was created in;
3. Run the following command:

```
$ openssl pkcs12 -export -inkey ./stream_admin.key -in ./stream_admin.pem -name StreamAdministrator -out ./stream_admin.p12
```

This will create a PKCS#12 file containing the PEM of the certificate and its private key in PKCS#8

format (encrypted). The previous utility will first ask the private key file pass phrase and then ask for a passphrase to protect the PKCS#12.



If using an openssl version greater than 3, you will need to add `-legacy` at the end of the command as the new version of the PKCS#12 is not widely supported.

4. Import this .p12 file into your certificate store or the certificate store of your browser if it has one (ex: Firefox). At the import, you should be prompted to enter the passphrase that you used to encrypt the PKCS#12.

Now you should have the certificate imported and ready to be used.

When going to the Stream web interface while not being logged in, your web browser should prompt you for a certificate to use and you should be able to select the one that you imported just now.

## Removing the administrator local account



Before deleting the account, ensure that your administrator certificate is working as intended.

1. Access Stream's web administration console and log in using the client certificate that was set-up at the previous step;
2. Browse to '**Security > Local accounts**';
3. Click the bin icon next to the '*administrator*' account and confirm deletion.



After reviewing the [\[install-guide:iaas-security::\\_security\\_guidelines\]](#), Stream is ready to leave its confined environment.

### 1.2.4. Security Guidelines

The following content are guidelines to have a secure Stream installation.

Stream should run on a dedicated machine. From this fact, all unused packages should be removed from the machine. The system should have been installed following the security guidelines recommended by the operating system vendor.

The following requirements should be met:

- SELinux should be enabled
- The `stream-hardening` rpm should be installed
- Privileged Access Management or SSH/Sudoers should be set up
- The firewall should be enabled and ports 80 and 443 allowed
- Only certificate authentication should be enabled once the product has been initialized and the initial Key Ceremony phase performed

- The NGINX configuration should be modified following the below procedure
- Stacktrace logging in events should be disabled

On top of that, though it is not mandatory, it is recommended to set up other security-related solutions, such as a Web Application Firewall, an Intrusion Detection System and a Security Information and Event Management.

All the following steps should be followed to ensure compliance if they are not already implemented with the above requirements, and should be done with an account with administrative privileges.

## SELinux

To enhance security, SELinux should be enabled.

```
# setenforce Enforcing
```

To ensure that it is enabled, run the following command

```
# getenforce
```

This should return **Enforcing**

## Install the stream-hardening rpm

Follow the same steps as in [install-guide:iaas-installation-stream::\_installing\_stream] but for the **stream-hardening** rpm.

Once the rpm is installed, a system reboot is necessary. The following command can be used:

```
# reboot now
```



In order to install the stream hardening policies, the server must have access to a repository (mirror, iso file, ...) of the linux distribution you are using in order to be able to install the dependencies of the software. The **stream-hardening** package has the following dependencies:

- **stream**
- **policycoreutils-python-utils**

Please note that these packages may have their own dependencies.

## Sudoers

To administrate Stream without using the root user, **stream-hardening** rpm creates a **stream-**

`administrator` group with sudoers permissions.

Create a new user with `stream-administrator` and `stream` groups, for instance, `user-admin`.

```
# useradd -G stream-administrator,stream user-admin
# passwd user-admin
```

Link `user-admin` to the selinux `sysadm_u` user

```
# semanage login -a -s sysadm_u -rs0:c0.c1023 user-admin
```



The `semanage` command is available with the `policycoreutils-python-utils` package.

Relabel the `user-admin` user home folder with the following command

```
# restorecon -FR -v /home/user-admin
```

In case you need to access the `user-admin` user account via ssh you will need to set the selinux `ssh_sysadm_login` boolean

```
# setsebool -P ssh_sysadm_login on
```



The `setsebool` command is available with the `policycoreutils` package.

Now the `user-admin` can:

- Manage mongodb server with `systemctl`
- Manage nginx server with `systemctl`
- Manage stream server with `systemctl`
- Execute every script under the folder `/opt/stream/sbin/` as a root user

## Configuring the Firewall

The firewall should have been configured at the setup step.

In addition to this configuration, the https (443) access should be restricted to :

- The Stream administrators
- External components using Stream certificate lifecycle capabilities (Stream for example)



Firewalld sometimes has default ports allowed. No other ports than those referenced in the setup step should be allowed.

## X509 Enforcing

In order to improve security once an administration certificate has been emitted, all authentication modes should be disabled apart from certificate authentication.

To do that, please follow the dedicated steps in the security section of the administration guide : **Managing Security › Enforce Certificate Authentication**

## NGINX Configuration

In order to improve security, the default NGINX configuration should be altered. In the configuration file in `/etc/nginx/nginx.conf`, the `server` instruction block containing the `listen 80` instruction should be deleted or commented.

Once an administration certificate has been emitted, the `/opt/stream/etc/stream-httpd.conf` should be updated. The following line

```
ssl_verify_client      optional_no_ca;
```

should be replaced by the lines

```
ssl_verify_client      on;
ssl_client_certificate  ssl/client-trusted-cas.pem;
ssl_trusted_certificate ssl/trusted-cas.pem;
ssl_crl                ssl/crl-bundle.pem;
```

This ensures only valid and trusted certificates can be used to authenticate on the Stream server.

For the following example chain :

**Root CA → Client Issuing CA 1**

**Root CA → Client Issuing CA 2**

The `/etc/nginx/ssl/client-trusted-cas.pem` file should contain the PEM certificates of the CAs trusted for client authentication, concatenated one after the other. It should look like:

```
-----BEGIN CERTIFICATE-----
<Client Issuing CA 1 PEM>
-----END CERTIFICATE-----
-----BEGIN CERTIFICATE-----
<Client Issuing CA 2 PEM>
-----END CERTIFICATE-----
```

The `/etc/nginx/ssl/trusted-cas.pem` file should contain the PEM certificates of the **chain** to the CAs trusted for client authentication, concatenated one after the other. It should look like:

```
-----BEGIN CERTIFICATE-----
```

```
<Root CA PEM>
-----END CERTIFICATE-----
```

Both these files should have the following permissions:

```
# chmod 640 /etc/nginx/ssl/trusted-cas.pem
# chmod 640 /etc/nginx/ssl/client-trusted-cas.pem
# chown root:nginx /etc/nginx/ssl/trusted-cas.pem
# chown root:nginx /etc/nginx/ssl/client-trusted-cas.pem
```

To update the CRL, the `/opt/stream/etc/crl-fetching.conf` configuration file (installed with the `stream-hardening` rpm) should be customized

```
# Uncomment and edit the following line
# CRL_URLS=("<CRL URL 1>" "<CRL URL 2>")
CRL_DOWNLOAD_PATH="/etc/nginx/ssl/tmp.crl"
CRL_PEM_PATH="/etc/nginx/ssl/tmp.crl.pem"
TMP_CRL_BUNDLE_PATH="/etc/nginx/ssl/tmp.crl.bundle"
NGINX_CRL_BUNDLE_PATH="/etc/nginx/ssl/crl-bundle.pem"
```

To customize this file, after the `# Uncomment and edit the following line` comment, the `CRL_URLS` line should be uncommented and edited to have each of your CRLs URLs.



**ALL** of your CAs present in the `/etc/nginx/ssl/trusted-cas.pem` and `/etc/nginx/ssl/client-trusted-cas.pem` files must have their CRL downloaded.



CRL are expected in DER format.



To fetch the CRL on stream first follow [Managing Certificate Revocation Lists](#) › **Configuring Certificate Revocation Lists for a Managed CA** in the administration guide, the CRL path is `http://localhost:9000/crls/<your CA Technical Name>`

The following file should then be put in `/etc/cron.d/nginx-crl`

```
# This cron runs every 5 minutes and execute a script replacing the CRL file for NGINX
*/5 * * * * root /opt/stream/sbin/crl-fetching
```

## Stacktraces management

Stacktraces in the functional logs can give a lot of information about the technical architecture of the application. To disable their logging, set the parameter `stream.event.disable-stacktrace` to `true` following the steps in the **Overridable configuration parameters** section of the administration guide.



Stacktraces are still available in the technical logs.

## 1.2.5. Upgrade

### Upgrade the Stream installation

The first step in the upgrade procedure is to upgrade the Stream component itself.

#### If Stream was installed using a repository

If you installed Stream using our repository (as described in the installation section), you should:

- Unpin the Stream version by commenting out any line excluding the `stream` package in the `/etc/yum.repos.d/stream.repo` repository file :

```
[stream]
enabled=1
name=Stream Repository
# exclude=stream
```

- Run `yum update stream`

Don't forget to pin the version again by uncommenting the line that was previously commented.

#### If Stream was installed manually

You must retrieve the latest Stream RPM from the EverTrust repository manually using the user credentials you were provided.

Connect to the server with an account with administrative privileges;

Install the Stream package with the following command:

```
# yum localinstall stream-2.1.x-1.x86_64.rpm
```

### Upgrade the database schema

Some Stream versions require that you run migration scripts against your database. Stream comes bundled with an `stream-upgrade` script that handles this migration logic.

Therefore, after each upgrade, you should run `stream-upgrade` to check whether new migrations should be run.

Connect to the server with an account with administrative privileges;

Run the following command:

```
# /opt/stream/sbin/stream-upgrade -t <target version>
```

In most cases, `stream-upgrade` can detect the version you're upgrading from by checking the database. If the source version is not automatically detected, you will encounter the following error:

```
*** Unable to infer the source version from your database. Specify it explicitly with the -s flag. ***
```

You'll have to explicitly tell `stream-upgrade` which version you are upgrading from. To do that, simply set the source version explicitly with the `-s` flag :

```
# /opt/stream/sbin/stream-upgrade -t <target version> -s <source version>
```

Similarly, `stream-upgrade` will try to use the MongoDB URI that was configured by the Stream configuration utility. If it fails to auto-detect your database URI or you wish to migrate another database, specify the URI explicitly using the `-m` flag:

```
# /opt/stream/sbin/stream-upgrade -t <target version> -m "<MongoDB connection string>"
```



The upgrade script requires the mongo shell MongoSH to connect to your database (`mongosh`). If this client is not installed on the host where Stream is running, consider installing the standalone `mongosh` client or running the upgrade script from another host that has access to the database.

## 1.2.6. Uninstallation



Before uninstalling, please ensure that you have a **proper backup of the Stream component**. Once uninstalled, all Stream data will be **irremediably lost!**

Uninstalling Stream consists in uninstalling:



- The Stream service;
- The MongoDB service;
- The NGINX service.

## Uninstalling Stream

Connect to the server with an account with administrative privileges;

Uninstall Stream with the following commands:

```
# systemctl stop stream
# yum remove stream
# rm -rf /opt/stream
# rm -rf /var/log/stream
# rm -f /etc/default/stream
```

## Uninstalling NGINX

Connect to the server with an account with administrative privileges;

Uninstall NGINX with the following commands:

```
# systemctl stop nginx
# yum remove nginx
# rm -rf /etc/nginx
# rm -rf /var/log/nginx
```

## Uninstalling MongoDB

Connect to the server with an account with administrative privileges;

Uninstall MongoDB with the following commands:

```
# systemctl stop mongod
# rpm -qa | grep -i mongo | xargs rpm -e
# rm -rf /var/log/mongodb
# rm -rf /var/lib/mongodb
```

## 1.3. Installing on Kubernetes

### 1.3.1. Installation

#### Concepts overview

In Kubernetes, applications are deployed onto **Pods**, which represents a running version of a containerized application. Pods are grouped by **Deployments**, which represent a set of Pods running the same application. For instance, should you need to run Stream in high availability mode, your deployment will contain 3 pods or more. Applications running in Pods are made accessible by a **Service**, which grants a set of Pods an IP address (which can either be internal to the cluster or accessible on the public Internet through a Load Balancer).

The recommended way of installing on Stream is through the Stream's Helm Chart. Helm is a package manager for Kubernetes that will generate Kubernetes resources necessary to deploy Stream onto your cluster. The official Helm Chart will generate a deployment of one or more Pods running Stream on your cluster.

#### Setting up Helm repository

Now that the application secrets are configured, add the **EverTrust Helm repository** to your machine:

```
$ helm repo add evertrust https://repo.evertrust.io/repository/charts
```

Verify that you have access to the Chart :

```
$ helm search repo evertrust/stream
NAME                CHART VERSION  APP VERSION  DESCRIPTION
evertrust/stream    0.2.0          2.0.0       EverTrust Stream Helm chart
```

## Configuring the namespace

For isolation purposes, we strongly recommend that you create a dedicated namespace for **Stream**:

```
$ kubectl create namespace stream
```

The namespace should be empty. In order to run Stream, you'll need to create two secrets in that namespace:

- A data secret containing your Stream license file and keyset.
- An image pull secret, allowing Kubernetes to authenticate to the EverTrust's container repository

## Creating the application secrets

You should have both a license file (most probably named `stream.lic`) and a keyset for your Stream installation.

To generate a keyset, download our [keyset utility](#) onto a secure environment that has access to your cluster. Extract the archive and run the binary that matches your architecture. For instance :

```
$ ./tinkey-darwin-arm64 generate-keyset --out=keyset.json
```

Then, create a Kubernetes secret containing both files into the Stream namespace :

```
$ kubectl create secret generic stream-data \  
  --from-file=license="<path to your license file>" \  
  --from-file=keyset="<path to your keyset file>" \  
  --namespace stream
```

## Creating the image pull secret

Next, you should configure Kubernetes to authenticate to the EverTrust repository using your credentials. They are necessary to pull the Stream docker image, you should have received them upon purchase. Get your username and password and create the secret:

```
$ kubectl create secret docker-registry evertrust-registry \  
  --docker-server=registry.evertrust.io \  
  --docker-username="<your username>" \  
  --docker-password="<your password>" \  
  --namespace stream
```

## Configuring the chart

You'll next need to override the defaults `values.yaml` file of the Helm Chart to reference the secrets

that we've created. We'll provide a minimal configuration for demonstration purposes, but please do follow our production setup guide before deploying for production.

Create a `override-values.yaml` file somewhere and paste this into the file:

```
image:
  pullSecrets:
    - evertrust-registry

license:
  secretName: stream-data
  secretKey: license

keyset:
  secretName: stream-data
  secretKey: keyset
```

To finish Stream's installation, simply run the following command:

```
$ helm install stream evertrust/stream -f override-values.yaml -n stream
```

Please allow a few minutes for the Stream instance to boot up. You are now ready to go on with the **first login**. This instance will allow you to test out if Stream is working correctly on your cluster. However, this installation is not production-ready. Follow our **production checklist** to make sure your instance is fit to run in your production environment.

## 1.3.2. First login

### Fetching the default administrator password

Allow a few seconds for your Stream instance to boot up. You can then fetch the administrator password that has been generated for your instance using the command :

```
$ kubectl exec $(kubectl get pods -n stream -l "app.kubernetes.io/name=stream" --sort -by={.status.podIP} -o jsonpath="{.items[0].metadata.name}") -n <namespace> -- /bin/sh -c "cat /stream/adminPassword"
```



The default administrator credentials are:

- Login: `administrator`
- Password: the one you got from the command above

### Manually creating the initial user


In case the automatic bootstrap process was disabled, you may need to manually create an

administrator user. Launch a MongoDB shell to access your database and run the following command to create the initial administrator:


```
db.security_accounts.insertOne({"identifier":"administrator","secret":"$6$96ZV/UmX1oMP  
UVA3$U5MejJB9S3jhqq1TDqhZMwV0cDX5BAWY3DL2nsxUHlpHj0LOfPuswy4nWjkMLify4FvKGKhEfADzljy7  
FGc8.", "permissions":[{"value":"configuration:*"}, {"value":"lifecycle:*"}], "roles":[],  
"type":"local"})
```

## Accessing the Stream Web Interface

1. Launch a web browser;
2. Browse to `https://[IP or DNS Name of the Stream component]/ui#`:



3. Specify the default administration credentials and hit the '**Login**' button:



It is **highly recommended** to delete the `adminPassword` file from your machine

once you saved it somewhere safe.

### 1.3.3. Production checklist

Even though the Helm Chart makes installing Stream a breeze, you'll still have to set up a few things to make Stream resilient enough to operate in a production environment.

#### Operating the database

All persistent data used by Stream is stored in the underlying MongoDB database. Therefore, the database should be operated securely and backed up regularly.

When installing the chart, you face multiple options regarding your database:

- By default, a local MongoDB standalone instance will be spawned in your cluster, using the `bitnami/mongodb` chart. No additional configuration is required but it is not production ready out of the box. You can configure the chart as you would normally below the `mongodb` key :

```
mongodb:
  architecture: replicaset
  # Any other YAML value from the chart docs
```

- If you want to use an existing MongoDB instance, provide the `externalDatabase.uri` value. The URI should be treated as a secret as it must include credentials:

```
externalDatabase:
  secretName: <secret name>
  secretKey: <secret key>
```

The chart doesn't manage the database. You are still in charge of making sure that the database is correctly backed up. You could either back up manually using `mongodump` or use a managed service such as MongoDB Atlas, which will take care of the backups for you.

#### Managing secrets

Storing secrets is a crucial part of your Stream installation. The keyset is the most important of them, being a master key used to encrypt and decrypt data before they enter the database. Alongside with other application secrets like your MongoDB URI (containing your credentials or certificate). We recommend that you create Kubernetes secrets beforehand or inject them directly into the pod.

Values that should be treated as secrets in this chart are:

Name	Description	Impact on loss
<code>keyset</code>	Master key used to encrypt sensitive data in database.	Highest impact: database would be unusable

Name	Description	Impact on loss
<code>events.secret</code>	Secret used to sign and chain events.	Moderate impact: events integrity would be unverifiable
<code>externalDatabase.uri</code>	External database URI, containing a username and password.	Low impact: reset the MongoDB password
<code>appSecret</code>	Application secret use to encrypt session data.	Low impact: sessions would be reset
<code>mailer.password</code>	SMTP server password	Low impact: reset the SMTP password

For each of these values, either :

- leave the field empty, so that a secret will be automatically generated.
- derive the secret value from an existing Kubernetes secret:

```
appSecret:
  secretName: <secret name>
  secretKey: <secret key>
```



Always store secrets in a safe place after they're generated. If you ever uninstall your Helm chart, the loss of the keyset will lead to the impossibility of recovering most of your data.

## High availability

By default, the chart will configure a single-pod deployment. This deployment method is fine for testing but not ready for production as a single failure could take down the entire application. Instead, we recommend that you set up a Stream cluster using at least 3 pods.

In order to do that, configure an `horizontalAutoscaler` in your `override-values.yaml` file:

```
horizontalAutoscaler:
  enabled: true
  minReplicas: 3
  maxReplicas: 3
```



Use `nodeAffinity` to spread your Stream cluster Pods among multiple nodes in different availability zones to reduce the risk of Single Point of Failure.

## Configuring ingresses

To create an ingress upon installation, simply set the following keys in your `override-values.yaml` file:

```
ingress:
  enabled: true
  hostname: stream.lab
  tls: true
```

## 1.3.4. Upgrade

We recommend that you only change values you need to customize in your `values.yml` file to ensure smooth upgrading. Always check the upgrading instructions between chart versions.

### Upgrading the chart

When upgrading Stream, you'll need to pull the latest version of the chart :

```
$ helm repo update evertrust
```

Verify that you now have the latest version of Stream (through the App version column) :

```
$ helm search repo evertrust/stream
NAME                CHART VERSION  APP VERSION  DESCRIPTION
evertrust/stream    0.2.0          2.0.0       EverTrust Stream Helm chart
```

Launch an upgrade by specifying the new version of the chart through the `--version` flag in your command :

```
$ helm upgrade stream evertrust/stream \
  --values override-values.yaml \
  --version 0.2.0
```

The chart will automatically create a `Job` that runs an upgrade script when it detects that the Stream version has changed between two releases. If the upgrade job fails to run, check the job's pod logs. When upgrading from an old version of Stream, you may need to explicitly specify the version you're upgrading from using the `upgrade.from` key.



Before upgrading to specific chart version, thoroughly read any `Specific chart upgrade instructions` for your version.

### Specific chart upgrade instructions

#### Upgrade to 1.7.0

- Switching to native kubernetes leases implementation. CRDs leases aren't used anymore.

## 1.3.5. Uninstallation

To uninstall Stream from your cluster, simply run :

```
$ helm uninstall stream -n stream
```

This will uninstall Stream. If you installed a local MongoDB instance through the Stream's chart, it will also be uninstalled, meaning you'll lose all data from the instance.



Before uninstalling Stream, if you wish to keep your database, please back up your application secrets (in particular the keyset). Without it, you won't be able to decrypt your database and it will become useless.

## 1.3.6. Advanced usage

Some edge use-cases might not have been included in the previous installation documentation, for clarity purposes. You may find some of them below.

### Running behind a container registry proxy

If your installation environment requires you to whitelist images that can be pulled by the Kubernetes cluster, you must whitelist the `registry.evertrust.io/stream` and `registry.evertrust.io/stream-upgrade` images. It is then possible to override the images being pulled by setting the `global.imageRegistry` key in your `values.yaml` file to point to your private registry:

```
global:  
  imageRegistry: <YOUR-PRIVATE-REGISTRY>
```

### Leases

To ensure clustering issues get resolved as fast as possible, Stream can use Kubernetes leases. We strongly recommend that you use this safety mechanism. However, the feature can be disabled by setting the `leases.enabled` key to `false`.

## 1.4. Monitoring

### Healthchecks

#### Liveness check

The liveness check is available on the `/alive` route of the pekko management port (7626 by default).

It checks that the pekko cluster is operational and performs a ping on the mongo database.

## Readiness check

The readiness check is available on the `/ready` route of the pekko management port (7626 by default).

It checks that the pekko cluster is operational and verifies that the instance has been bootstrapped.



For RPM configuration, this check is proxied by the default NGINX configuration, and available on `/ready`

## Metrics

### Basic

To enable basic prometheus metrics on port 9095, the following configuration must be applied.

```
kamon {
  modules {
    prometheus-reporter.enabled = yes
    apm-reporter.enabled = no
    host-metrics.enabled = no
    jvm-metrics.enabled = no
  }

  prometheus {
    include-environment-tags = true
    embedded-server {
      hostname = 0.0.0.0
      port = 9095
    }
  }
}
```

### Stream

Stream specific metrics can also be exposed on the prometheus endpoint using this configuration parameter:

```
stream.metrics.enabled = true
```

These metrics include:

- License expiration information
- Stream version
- Scala version
- CRL expiration

- CRL generation
- Signer (CA/TSA/OCSP) expiration
- Keystore status
- Credentials expiration
- Last user activity



Additional metrics configuration such as refresh intervals can be found on the configuration reference page.

## 1.5. Troubleshooting

### Stream Doctor

Stream doctor is a tool that performs checks on your Stream installation as well as its dependencies to ensure that everything is configured properly. Note that the tool requires root permissions to run.

#### Checks performed

At the moment, Stream doctor checks for :

##### OS checks

- Checks for installed Stream version, MongoDB version, Java version, Nginx Version and OS version.
  - If the OS is a RedHat distribution, checks for RedHat subscription
  - If Mongo is not installed locally, it notices it as an information log
- Checks for **SELinux**'s configuration
  - If selinux is disabled nothing has to be checked
  - If selinux is enforced checks the **httpd\_can\_network\_connect** sebool value
- Checks for the status of the necessary services: **mongod**, **nginx** and **stream**.
- Checks how long the **stream service** has been running for.
- Checks if there is an **NTP service** active on the machine and checks if the system clock is synchronized with the NTP service.

##### Config checks

- Checks for existence and permissions of the **configuration** file: the permissions are expected to be at least 640 and the file is supposed to belong to stream:stream.
- Checks for existence and permissions of the **licence** file: the permissions are expected to be at least 640 and the file is supposed to belong to stream:stream.
- Checks for existence and permissions of the **keyset** file: the permissions are expected to be

exactly 600 and the file is supposed to belong to stream:stream.

- Checks for existence and permissions of the Stream directory (default : /opt/stream) : the permission is expected to be at least 755
- Checks for the existence of the **symbolic link** for **nginx configuration** and runs an **nginx -t** test.
- Retrieves the **Java heap size parameters** that were set for Stream and informs the user if the default ones are used (min = 2048 and max = 3072).
- Retrieves the **Stream DNS hostname** and raises an error if it has not been set.
- Retrieves the **MongoDB URI** (throws a warning if MongoDB is running on localhost; throws an error if MongoDB is running on an external instance but the *authSource=admin* parameter is missing from the URI).
- Parses the **licence file** to retrieve its expiration date.
- Checks for the existence of the file containing the initial administrator password and throws a warning if that file still exists (displays the password too)

## Network checks

- Runs a **MongoDB ping** on the URI, then checks for the database used in the URI (throws a warning if the database used is not called *stream*; throws an error if no database is specified in the URI).
- Checks for **Pekko High Availability** settings: if no node hostname is set up, skips the remaining HA checks. If 2 nodes are set up, retrieves which node is running the doctor and checks for the other node. If 3 nodes are set up, retrieves which node is running the doctor and checks for the other 2 nodes. The check runs as:
  - if *curl* is installed, runs a *curl* request on the Node hostname at *alive* on the management port (default is 7626), and if *alive* runs another *curl* request on the Node hostname at */ready* on the management port. Both requests should return HTTP/200 if ok, 000 otherwise.
  - if *curl* is not installed, uses the built-in Linux TCP socket to run TCP SYN checks on both the HA communication port (default is 25520) and the management port (default is 7626) on the Node hostname.
- Checks for **firewall configuration**. Currently only supports *firewalld* (RHEL) and a netstat test.
  - The **netstat part** will run a *netstat* command to check if the JVM listening socket is active (listening on port 9000). If *netstat* is not installed, it will skip this test.
  - The **firewalld part** will check if the HTTP and HTTPS services are opened in the firewall and if it detected a HA configuration, it will check if the HA ports (both of them) are allowed through the firewalld. If *firewalld* is not installed or not active, it will skip this test.
- Checks if IPv6 is active on each network interface and raises a warning if it is the case (with the interface name).

## TLS checks

- Checks for existence and permissions of the **Stream server certificate** file: the permissions are expected to be at least 640 and the file is supposed to belong to the nginx group.

- Parses the **Stream server certificate** file: it should be constituted of the actual TLS server certificate first, then of every certificate of the trust chain (order being leaf to root). It throws a warning if the certificate is self-signed or raises an error if the trust chain has not been imported. It otherwise tries to reconstitute the certificate trust chain via the *openssl verify* command, and throws an error if it cannot.
- Parses the **Stream server certificate** file and checks if the **Stream hostname** is present in the **SAN DNS names** of the certificate, throws an error if it is not there.

## Log packing option

If the Stream doctor is launched with the *-l option*, it will pack the logs of the last 7 days (in */opt/stream/var/log*) as well as the startup logs (the */var/log/stream/stream.log* file) and create a tar archive.

The *-l option* accepts an optional parameter that should be an integer (1-99) and will pack the logs of the last n days instead, as well as the startup logs.

Note that the **Stream doctor** will still perform all of its check; the log packing is done at the very end of the program.

Example of call to pack the logs of the last 7 days :

```
# /opt/stream/sbin/stream-doctor -l
```

Example of call to pack the logs of the last 30 days :

```
# /opt/stream/sbin/stream-doctor -l 30
```

## Saving the doctor's output

If the Stream doctor is launched with the *-o option*, it will perform all of its checks and save the output in the specified file instead of displaying it into the stdout (default is the commandline interface).

If you use the option, you must provide a filepath in a writable directory.

Example of call to save the output in a file named *stream-doctor.out* instead of the stdout :

```
# /opt/stream/sbin/stream-doctor -o stream-doctor.out
```

## Direct fixes

The Stream doctor is able to fix the following issues directly by itself if you use the *--fix* flag with the script:

- If the application secrets (play secret and event seal secret) have not been changed, the doctor will generate random application secrets and provide them to Stream directly (requires you to manually restart Stream afterwards);
- If firewalld is not allowing HTTP and HTTPS traffic, the doctor will change the firewall settings to allow **both** protocols and then restart the firewall by itself;
- If some permissions for the configuration file, the license file or the keyset file are not what they should be, the doctor will change these permissions (file owner and rwx permissions) to be what they should.

## Help menu

To display Stream doctor's help menu, use the *-h option*.

## 1.6. Advanced configuration

Some technical configurations can be applied to an instance directly in its configuration file. This should be used carefully as it may cause things to break.

### Injecting advanced configuration

#### RPM

On VMs, you have access to the `/opt/stream/etc/conf.d/stream-extra.conf` file. For each parameter you wish to override, create a newline and use the following syntax:

```
<parameter>=<value>
```

As an example, if you want to modify the file extension that DER certificates will have when sent as email attachments and set it to CRT, you need to add:

```
stream.metrics.enabled=true
```

After modifying the file, restart the Stream service:

```
$ systemctl restart stream
```



One added line means one modified option, you need to add as many lines at the end of the file as there are values that you want to override.

#### Kubernetes

The Stream container provides a bundled `application.conf` file that is mostly configured through environment variables. To modify low-level behavior of Horizon that are not accessible through an environment variable, use the `extraConfig` value in your `values.yaml` file to update specific settings:

```
extraConfig: |
  stream {
    metrics.enabled = true
  }
```

Extra configurations are appended at the end of the config file, overriding any previously set config value.

## Available settings



Parameter `stream.security.http.headers.xapi.idprov` was deleted.



Parameter `stream.security.http.headers.xapi.key` was deleted.



Parameter `stream.security.http.headers.xapi.id` was deleted.



Parameter `stream.security.http.headers.xid` was deleted.



Parameter `stream.trustchain.ca.online.root.operational` was deleted.



Parameter `stream.trustchain.ca.online.root.non_operational` was deleted.



Parameter `stream.trustchain.ca.online.subordinate.operational` was deleted.



Parameter `stream.trustchain.ca.offline.root.non_operational` was deleted.



Parameter `stream.crl.manager.timeout` was deleted.



Parameter `stream.ocsp.manager.timeout` was deleted.



Parameter `stream.timestamping.manager.timeout` was deleted.



Parameter `stream.crl.queue.size` was deleted.

## Bootstrap Configuration

### `stream.bootstrap.administrator.name`

```
stream.bootstrap.administrator.name = "administrator"
```

Default administrator account name

### `stream.bootstrap.administrator.display-name`

```
stream.bootstrap.administrator.display-name = "Stream Administrator"
```

Default administrator account display name



This parameter replaces `stream.bootstrap.administrator.display.name`. Please modify your configuration accordingly

## **stream.bootstrap.administrator.password.path**

```
stream.bootstrap.administrator.password.path = "var/run/adminPassword"
```

Relative path of the file where the initial admin password should be stored into

## **stream.bootstrap.local.identity.provider**

```
stream.bootstrap.local.identity.provider = "local"
```

Length (in bytes) of the initial admin password

Default administrator account identity provider to use

## **stream.bootstrap.timeout**

```
stream.bootstrap.timeout = "1m"
```

Duration after which the bootstrap of Stream times out

## **CRL Configuration**

### **stream.crl.sync.interval**

```
stream.crl.sync.interval = "15m"
```

Interval at which CRL synchronization occurs

### **stream.crl.cache.max-age.mode**

```
stream.crl.cache.max-age.mode = "1s"
```

How to set max-age cache directive on crl fetch: one of 'disabled', 'nextrefresh' or a duration

### **stream.crl.cache.max-age.default**

```
stream.crl.cache.max-age.default = "5m"
```

Default max-age duration in 'nextrefresh' mode when the CRL has no next refresh planned

## **stream.crl.upload.max-size**

```
stream.crl.upload.max-size = "20m"
```

Max allowed size on applicative side for CRL uploads

## **Certificate authentication**

### **stream.security.http.headers.certificate**

```
stream.security.http.headers.certificate = null
```

Name of the HTTP header containing the certificate

### **stream.security.authentication.enforce-x509**

```
stream.security.authentication.enforce-x509 = false
```

Allow only certificate authentication

## **Event Configuration**

### **stream.event.ttl**

```
stream.event.ttl = null
```

Time to live of the events. If not set, events never expire

### **stream.event.chainsign**

```
stream.event.chainsign = true
```

Specify whether to chain and sign the Stream events to ensure they haven't been tampered with

### **stream.event.seal.algorithm**

```
stream.event.seal.algorithm = "HS512"
```

Algorithm to use to hash the signature of the events in Stream (other possible values are "HS384" and "HS256")

### **stream.event.seal.secret**

```
stream.event.seal.secret = null
```

Secret to seal the events with

### **stream.event.ignore-unsealed-pending**

```
stream.event.ignore-unsealed-pending = false
```

Do not throw an error if pending events are unsealed

### **stream.event.disable-stacktrace**

```
stream.event.disable-stacktrace = false
```

Enable to remove stacktraces from Stream events

### **stream.event.timeout**

```
stream.event.timeout = "30s"
```

Duration after which the event manager times out when trying to retrieve the last signed event in the database

### **stream.event.manager.interval**

```
stream.event.manager.interval = "5s"
```

How often will the Event Manager actor check in the database if new a new event appeared to sign it and display it in the "Events" section of Stream

## **General**

### **stream.security.trustmanager.enforce-serverauth**

```
stream.security.trustmanager.enforce-serverauth = false
```

If set to true, enforces the use of the serverAuth EKU in the server authentication certificates (when Stream accesses a service through TLS)



This parameter replaces `stream.security.trustmanager.enforce_serverauth`. Please

modify your configuration accordingly

### **stream.security.trustmanager.timeout**

```
stream.security.trustmanager.timeout = "10s"
```

Timeout to check trust status of certificates



This parameter replaces `stream.trust.manager.timeout`. Please modify your configuration accordingly

### **stream.security.trustmanager.cache.expire-after-access.external**

```
stream.security.trustmanager.cache.expire-after-access.external = "30d"
```

Time after which an entry in the CRL cache expires for external CAs



This parameter replaces `stream.trust.manager.cache.external.expireafteraccess`. Please modify your configuration accordingly

### **stream.security.trustmanager.cache.expire-after-access.managed**

```
stream.security.trustmanager.cache.expire-after-access.managed = "5m"
```

Time after which an entry in the CRL cache expires for managed CAs



This parameter replaces `stream.trust.manager.cache.managed.expireafteraccess`. Please modify your configuration accordingly

### **stream.security.trustmanager.crl-info.interval**

```
stream.security.trustmanager.crl-info.interval = "5m"
```

Interval at which CRL Info are synchronized in trust manager

### **stream.security.manager.timeout**

```
stream.security.manager.timeout = "10s"
```

Duration after which the security manager times out when trying to authenticate a principal with its session

## **stream.security.principal.password.length**

```
stream.security.principal.password.length = 42
```

Local accounts password length



This parameter replaces `stream.account.secret.length`. Please modify your configuration accordingly

## **stream.keystore.timeout**

```
stream.keystore.timeout = "1m"
```

How long the authentication cache lasts

Timeout for operations using keystores (generating CSR, listing keys, etc ..)

## **stream.keystore.pkcs11.reload.delay**

```
stream.keystore.pkcs11.reload.delay = "5s"
```

Delay when reloading pkcs11 keystores after an error

## **stream.keystore.healthcheck.interval**

```
stream.keystore.healthcheck.interval = "5m"
```

Interval at which keystore status is checked

## **stream.keystore.required-for-readiness**

```
stream.keystore.required-for-readiness = []
```

List of names of keystores that are required to consider the instance ready

## **stream.queue.timeout**

```
stream.queue.timeout = "5s"
```

Timeout to register the queues in actors

## stream.queue.parallelism

```
stream.queue.parallelism = 5
```

Number of parallel requests (enrollment, revocation, ocsrp, timestamping...) on the default queue



This parameter replaces `stream.queue.default.parallelism`. Please modify your configuration accordingly

## stream.queue.size

```
stream.queue.size = 100
```

Number of requests (enrollment, revocation, ocsrp, timestamping, crl, krl) that can be queued on the default queue



This parameter replaces `stream.queue.default.size`, `stream.crl.queue.size`. Please modify your configuration accordingly

## stream.metrics.enabled

```
stream.metrics.enabled = false
```

Enable advanced metrics for collection

## stream.metrics.intervals.short

```
stream.metrics.intervals.short = "30s"
```

Interval at which short lived metrics are computed

## stream.metrics.intervals.long

```
stream.metrics.intervals.long = "5m"
```

Interval at which background metrics are computed

## stream.trigger.timeout

```
stream.trigger.timeout = "1m"
```

Timeout for registering the triggers in actors

## stream.ntp.client.timeout

```
stream.ntp.client.timeout = "1m"
```

Timeout for registering the NTP Clients in actors

## stream.system.monitor.timeout

```
stream.system.monitor.timeout = "1m"
```

Timeout for the system monitor loading



This parameter replaces `stream.system.configuration.timeout`. Please modify your configuration accordingly

## stream.sql.max-recursion-depth

```
stream.sql.max-recursion-depth = 5
```

Maximum recursion allowed for the SQL (Stream Query Language) queries

## HTTP Headers Configuration

### stream.security.http.headers.enforce-connection-close

```
stream.security.http.headers.enforce-connection-close = true
```

Defines whether HTTP connections should remain open



This parameter replaces `stream.http.header.enforce_connection_close`. Please modify your configuration accordingly

### stream.security.http.headers.real-ip

```
stream.security.http.headers.real-ip = "X-Real-IP"
```

Name of the HTTP header to use as Real IP



This parameter replaces `stream.http.header.realip`. Please modify your configuration accordingly

## KRL Configuration

### **stream.krl.sync.interval**

```
stream.krl.sync.interval = "15m"
```

Interval at which KRL synchronization occurs

### **stream.krl.cache.max-age.mode**

```
stream.krl.cache.max-age.mode = "1s"
```

How to set max-age cache directive on krl fetch: one of 'disabled', 'nextrefresh' or a duration

### **stream.krl.cache.max-age.default**

```
stream.krl.cache.max-age.default = "5m"
```

Default max-age duration in 'nextrefresh' mode when the KRL has no next refresh planned

## Keyset configuration

### **stream.secret.manager.keyset.path**

```
stream.secret.manager.keyset.path = "etc/stream.keyset"
```

Path to the keyset for secrets encryption

### **stream.secret.manager.keyset.master-key-uri**

```
stream.secret.manager.keyset.master-key-uri = null
```

Master key URI to encrypt the keyset with

## OCSP Configuration

### **stream.ocsp.timeout**

```
stream.ocsp.timeout = "1m"
```

Timeout for processing OCSP requests and starting OCSP actors

## stream.ocsp.request.max-size

```
stream.ocsp.request.max-size = "8k"
```

Max allowed size for OCSP requests



This parameter replaces `stream.ocsp.request.maxsize`. Please modify your configuration accordingly

## stream.ocsp.default-next-update-delay

```
stream.ocsp.default-next-update-delay = "5m"
```

Default time for OCSP response next update when no crl refresh is available



This parameter replaces `stream.ocsp.default.next_update_delay`. Please modify your configuration accordingly

## OpenID Configuration

### stream.openid.state-separator

```
stream.openid.state-separator = "#"
```

Separator character of the OpenID state



This parameter replaces `stream.security.identity.provider.openid.state.separator`. Please modify your configuration accordingly

### stream.openid.nonce.size

```
stream.openid.nonce.size = 32
```

Size (in bytes) of the challenge stored in the nonce



This parameter replaces `stream.security.identity.provider.openid.nonce.size`. Please modify your configuration accordingly

### stream.openid.nonce.ttl

```
stream.openid.nonce.ttl = "1m"
```

Duration for which a nonce stays in Horizon before being removed



This parameter replaces `stream.security.identity.provider.openid.nonce.ttl`. Please modify your configuration accordingly

## SSH Configuration

### `stream.ssh.ca.timeout`

```
stream.ssh.ca.timeout = "1m"
```

Timeout for registering the SSH Certificate Authorities in actors

The Timeout of SSH CA actions

## Search Configuration

### `stream.security.principal.search.page.default-size`

```
stream.security.principal.search.page.default-size = 50
```

How many elements to retrieve in a security principals search query if no pageSize has been specified



This parameter replaces `stream.security.principal.search.page.default_size`. Please modify your configuration accordingly

### `stream.security.principal.search.page.max-size`

```
stream.security.principal.search.page.max-size = null
```

How big can the pageSize parameter be in a security principals search query (Must be a positive integer)



This parameter replaces `stream.security.principal.search.page.max_size`. Please modify your configuration accordingly

### `stream.event.search.page.default-size`

```
stream.event.search.page.default-size = 50
```

How many elements to retrieve in an event search query if no pageSize has been specified



This parameter replaces `stream.event.search.page.default_size`. Please modify your configuration accordingly

### **stream.event.search.page.max-size**

```
stream.event.search.page.max-size = null
```

How big can the pageSize parameter be in an event search query (Must be a positive integer)



This parameter replaces `stream.event.search.page.max_size`. Please modify your configuration accordingly

### **stream.x509.certificate.search.page.default-size**

```
stream.x509.certificate.search.page.default-size = 50
```

How many elements to retrieve in a X509 certificate search query if no pageSize has been specified



This parameter replaces `stream.certificate.search.page.default_size`. Please modify your configuration accordingly

### **stream.x509.certificate.search.page.max-size**

```
stream.x509.certificate.search.page.max-size = null
```

How big can the pageSize parameter be in a X509 certificate search query (Must be a positive integer)



This parameter replaces `stream.certificate.search.page.max_size`. Please modify your configuration accordingly

### **stream.ssh.certificate.search.page.default-size**

```
stream.ssh.certificate.search.page.default-size = 50
```

How many elements to retrieve in a SSH certificate search query if no pageSize has been specified

### **stream.ssh.certificate.search.page.max-size**

```
stream.ssh.certificate.search.page.max-size = null
```

How big can the pageSize parameter be in a SSH certificate search query (Must be a positive integer)

integer)

## TSA Configuration

### **stream.timestamping.timeout**

```
stream.timestamping.timeout = "1m"
```

Timeout to register signers and process responses

### **stream.timestamping.authority.timeout**

```
stream.timestamping.authority.timeout = "1m"
```

Timeout to register timestamping authorities in actors

### **stream.timestamping.request.max-size**

```
stream.timestamping.request.max-size = "8k"
```

Max allowed size for timestamping requests



This parameter replaces `stream.timestamping.request.maxsize`. Please modify your configuration accordingly

## X509 Configuration

### **stream.x509.ca.timeout**

```
stream.x509.ca.timeout = "1m"
```

Timeout for registering the X509 Certificate Authorities in actors

The Timeout of X509 CA actions



This parameter replaces `stream.ca.timeout`. Please modify your configuration accordingly

## 2. Admin guide

## 2.1. Introduction

### Description

Stream is EverTrust Certificate Authority solution and is powered up by:

- Pekko
- BouncyCastle
- MongoDB
- Kamon
- Play! Framework
- Scala
- NGINX
- Vue.js
- Quasar

This document is specific to Stream version **2.1**, and may apply to follow-up minor releases.

### Scope

This document is an administration guide detailing how to configure and operate Stream.

### Out of Scope

This document does not describe how to install and bootstrap a Stream instance. Please refer to the installation guide for installation related tasks.

## 2.2. Managing Certification Authorities

### 2.2.1. Importing an External Certification Authority

1. Log in to the Stream Administration Interface.

2. Go to **Certification Authorities** > **External CAs** and click on  .

3. You need to provide the X509 CA Certificate, either by pasting it directly into the box or by importing the file. **PEM** and **DER** formats are supported. Then click "Next".

4. In the **Details** tab, check if the details that were parsed from the certificate match those of the CA you wish to import. If it does, click "Next".

5. In the **Configuration** tab, you can

- Add a **CRL**

- Edit the **Refresh period**
- Edit the **Timeout timer**
- Configure a **proxy**
- Toggle whether the external CA should be trusted for **server authentication** or **client authentication**
- Specify the **Outdated Revocation Status Policy**
- Enable OCSP and configure a **Default OCSP Signer**

6. You can then click the "Import" button in the bottom right corner to import your CA.


If everything was ok, you should see your CA marked as *external* if you go to **Certification Authorities > Trust chains**:



## 2.2.2. Importing an existing Managed Certification Authority

1. Log in to the Stream Administration Interface.
2. Go to **Import existing CA** from the menu on the left
3. Import your CA certificate file or paste the content of the file in the *Copy/paste the certificate* box. If you decide to paste the file's content, don't forget to click the parse button (📄) on the right before continuing.
4. Scroll down to the bottom of the page and check the certificate's information. If everything is correct, click "Next".
5. Select the Keystore where your CA's key is stored. If you do not have a keystore set up yet, please refer to the *Managing Keystores & Keys* section.
6. Select the key that was used to generate the CA from the selected keystore and click "Next".
7. Upload your CA's CRL file and click "Add".

If everything was ok, you should see your CA marked as *managed* if you go to **Certification Authorities > Trust chains**:



## 2.2.3. Issuing a new Root Certification Authority

1. Log in to the Stream Administration Interface.
2. Go to **Create a new CA** from the menu on the left.
3. Input your CA's **internal name** and manage the **DNs** that you want to add (using the **Add a DN element** button on the bottom left corner) or to remove (using the  icon).
4. Select the **Keystore** that contains the key you want to use to generate this CA, then select the key(s) that you want to use. If you do not have a keystore set up yet, please refer to the **Managing Keystores & Keys** section.
5. Select **Selfsigned** as a signing method, and pick the hash algorithm of your choice. Optionally, if you picked a PKCS#11 Keystore and an RSA key, you have the ability to use a PSS signature instead of the classic PKCS#1 one : if you wish to do so, just turn on the toggle. Note that your HSM must support the **CKM\_RSA\_PKCS\_PSS** mechanism.
6. Set the **lifetime** of your CA in days. Optionally, you can set up a **backdate** and a **path length**. Once you are done, click "Add".
7. You can directly configure your CA from this menu, by turning on or off **enrollment**, trusting the CA for **client authentication** or **server authentication**, enabling **OCSP** or **enforcing key unicity**. Once you're satisfied with your settings, click "Add".

If everything was ok, you should see your CA marked as **managed** on a new trust chain if you go to **Certification Authorities > Trust chains**:




## 2.2.4. Issuing a subordinate Certification Authority

### Signed locally

1. Log in to the Stream Administration Interface.
2. Go to **Create a new CA** from the menu on the left.
3. Input your CA's **internal name** and manage the **DNs** that you want to add (using the **Add a DN element** button on the bottom left corner) or to remove (using the  icon).
4. Select the **Keystore** that contains the key you want to use to generate this CA, then select the key(s) that you want to use. If you do not have a keystore set up yet, please refer to the **Managing Keystores & Keys** section.
5. Select **Signed with an internal CA** as the signing method.
6. Select the **Managed CA** you want to sign the certificate with.
7. Set the **lifetime** of your CA in days. Optionally, you can set up a **backdate** and a **path length**.
8. Optionally, you can set up an **OID Policy**, a **CPS Pointer**, add **CRLDPs** and the CA's **AIA**. Once you are finished with the settings, click "Issue CA".
9. You can directly configure your CA from this menu, by turning on or off **enrollment**, trusting the CA for **client authentication** or **server authentication**, enabling **OCSP** or **enforcing key unicity**. Additionally, if you issued this CA using an RSA key from a PKCS#11 keystore, you can choose to use the PSS signature algorithm instead of the default PKCS#1 one to sign new certificates. To do so, simply turn on the toggle. Note that your HSM must support the **CKM\_RSA\_PKCS\_PSS** mechanism. Once you're satisfied with your settings, click "Add".

If everything was ok, you should see your CA marked as **managed** on a new trust chain if you go to **Certification Authorities > Trust chains**:




### Signed externally

1. Log in to the Stream Administration Interface.
2. Go to **Create a new CA** from the menu on the left.

3. Input your CA's **internal name** and manage the **DNs** that you want to add (using the **Add a DN element** button on the bottom left corner) or to remove (using the  icon).
4. Select the **Keystore** that contains the key you want to use to generate this CA, then select the key(s) that you want to use. If you do not have a keystore set up yet, please refer to the **Managing Keystores & Keys** section.
5. Select **Signed with an external CA** as the signing method.
6. Click the link in the **Export** section to download the **CSR** for your CA, then sign it using your external CA and export the signed certificate under PEM or DER format.
7. Upload the signed certificate in the **Import** section.
8. Scroll down to the bottom of the page and check the certificate's information. If everything is correct, click "Next".
9. You can directly configure your CA from this menu, by turning on or off **enrollment**, trusting the CA for **client authentication** or **server authentication**, enabling **OCSP** or **enforcing key unicity**. Once you're satisfied with your settings, click "Add".

If everything was ok, your should see your CA marked as **managed** on a new trust chain if you go to **Certification Authorities > Trust chains**:



## 2.2.5. Note on CRLDP and AIA settings



Regardless of the CA type, the setting "CRLDP" refers to the CRL of the CA you are configuring, and **NOT** the one of the issuing CRL. Same goes for the AIA: you need to specify the certificate of the CA you are configuring, and not the certificate of its issuing CA.

## 2.2.6. AIA Certificate Issuer

Stream allows you to download the **Certificate** of the **CAs** (external and managed). This is usually used in AIA issuer certificate extension to be able to download the certificate of the issuing Certificate Authority.

The standard download URL format is `http(s)://[stream_url]/aias/CA_internal_name`. This URL can be accessed by anyone without prior authentication, either through HTTP or HTTPS.

You need to specify the **Internal name** of the CA to download its **certificate** and not its **Common Name (CN)**.

The certificate format depends on the request **ACCEPT** header:

- **application/x-pem-file**: returns the certificate in **PEM**
- **application/pkix-cert**: returns the certificate in **DER**
- **application/x-pkcs7-certificates**: returns the certificate in **PKCS7**

If no **ACCEPT** header is specified, return the certificate in **DER**.

The certificate is returned with the following headers:

- **Content-Type**:
  - **application/x-pem-file** for **PEM**
  - **application/pkix-cert** for **DER**
  - **application/x-pkcs7-certificates** for **PKCS7**
- **Content-Disposition**: 'attachment; filename=<ca name>'

## 2.3. Managing Certificate Revocation

### 2.3.1. Configuring Certificate Revocation Lists for an External CA

1. Log in to the Stream Administration Interface ;
2. Go to **Certification Authorities > External CAs** and click on  next to the name of the CA you want to import the CRL of ;
3. Select a valid CRL file that has been signed by your CA ;
4. If everything went through correctly, the CRL of that external CA should be available to download from Stream ;
5. Additionally, if you want to push the CRL into a CRL storage, click  on the external CA ;

5.1 In the **Configuration** tab, select one or several previously created external storages from the drop-down menu:

- **On CRL update**: this will be triggered every time a new CRL is uploaded (see step 2).
- **On CRL sync**: this will trigger every 15 minutes to ensure CRL is up to date on the storage, and push the new one if needed


5.2 Click the **Save** button at the top.

The CRL should now also be pushed in the CRL storage(s) whenever you manually import it into Stream. Note that the CRL will still be accessible from the standard Stream CRLDP.

## 2.3.2. Configuring Certificate Revocation Lists for a Managed CA

To manage the **CRLs** of a managed CA, you first need to set up a **CRL Policy**:

1. Log in to the Stream Administration Interface.
2. Go to **Certification Authorities > Managed CAs** and click on  next to the name of the CA you want to edit the CRL policy of.
3. Go under the **CRL/OCSP** tab.
4. First, you need to define the validity period of your CRL, i.e. the period of time while your CRL is considered valid. The countdown starts at the moment the CRL is generated. If you want your CRLs to be valid for a week, you can type **7 days**.
5. You can then automate the **CRL generation** using either the **Hard CRL generation**, the **Lazy CRL generation** or both of them in combination:
  - The **Hard CRL generation** parameter takes a cron expression in Quartz format and generates the CRL every time that cron expression is valid, without any condition. It is recommended to generate the **CRLs** every day. To generate a new **CRL** every day at 1 A.M., the cron expression is: `0 0 1 * * ?`
  - The **Lazy CRL generation** parameter takes a cron expression in Quartz format and checks if the CRL needs to be updated, i.e. if a certificate has been revoked, since the last CRL generation. If a certificate has been revoked since the last generation then a new CRL will then be generated, otherwise it will do nothing. It is recommended to have a short time span for the lazy generation so that the CRL always stays up to date. To check for possible CRL updates every 5 minutes, the cron expression is: `0 0/5 * * * ?`



6. Click the **Save** button at the top of the page.

Now your CRL policy has been configured, and you've been redirected to the Managed CAs page.

You can then generate manually the CA's first CRL using the  button next to the CA's name that you just configured. If you configured the **Hard** or the **Lazy** generation, your CRL will then automatically be updated according to the cron quartz expression you specified.

7. Additionally, if you want to push the CRL into other storages, click  on the managed CA ;

**7.1** In the **Configuration** tab, select one or several previously created external storages from the drop-down menu:

- **On CRL generation**: this will be triggered every time a new CRL is generated (manually or via

the configuration at step 5).

- **On CRL sync:** this will trigger every 15 minutes to ensure CRL is up to date on the storage, and push the new one if needed

7.2 Click the **Save** button at the top.

The CRL should now also be pushed in other storages. Note that the CRL will still be accessible from the standard Stream CRLDP.

### 2.3.3. Viewing CRLs

1. Log in to the Stream Administration Interface.

2. Go to **Revocation Management > CRLs**.

3. You can then see information regarding your CAs' CRLs that are going to be detailed below:

CA	Number	Last update	Next update	Next refresh	
SAGMCA2	15	Oct 3, 2022 10:17 AM +02:00	Oct 10, 2022 10:17 AM +02:00	Oct 3, 2022 10:20 AM +02:00	↓ ↻
SAGMCA3	c	Oct 3, 2022 10:17 AM +02:00	Oct 10, 2022 10:17 AM +02:00	Oct 3, 2022 10:20 AM +02:00	↓ ↻
SAGRCA2	1e	Oct 3, 2022 10:16 AM +02:00	Oct 10, 2022 10:16 AM +02:00	Oct 3, 2022 10:20 AM +02:00	↓ ↻

Records per page: 20 |< < 1/1 > >|

- The **CA** column indicates the name of the CA whose CRL is detailed in the line
- The **Number** column indicates the serial number of the CRL. It starts at 1 for the very first CRL generated and is incremented by 1 at each generation. It is displayed in hexadecimal format.
- The **Last update** column indicates the date and time when the current CRL was generated.
- The **Valid Until** column indicates the date and time when the current CRL will expire. It should be equal to *Last update* + the validity period you set in the **CRL policy** field.
- The **Next refresh** column indicates the date and time when the current CRL will be refreshed. It should be equal to the nearest date matching either cron quartz expression you set in the **CRL policy** field (lazy or hard).
- The **download** ↓ **button** allows you to download your CRL. It also serves as a CRLDP. For more information about CRLDPs in Stream, please refer to next section.
- The **generate** ↻ **button** allows you to manually refresh the CRL and generates a new one.
- The **refresh** ↻ **button** refreshes the information displayed in the tab, in case a generation happened in between. It **does not** refresh the CRLs, only the displayed information.

## 2.3.4. Downloading CRLs

Stream allows you to download the **CRLs** of the **CAs** it manages. The standard download URL format is `http(s)://[stream_url]/crls/CA_internal_name`. This URL can be accessed by anyone without prior authentication, either through HTTP or HTTPS.

You need to specify the **Internal name** of the CA to download its **CRL** and not its **Common Name (CN)**.

**CRLs** are by default generated and thus downloaded in **DER** format. You can specify `?form=PEM` at the end of the previously given URL to download the CRL in PEM format.

As an example, here are the **CRLDPs** of 2 different CAs that were set up through this guide:

- `https://stream.evertrust.fr/crls/SAGMCA2` will download the CRL for SAGMCA2 through HTTPS in DER format
- `http://stream.evertrust.fr/crls/SAGMCA3?form=PEM` will download the CRL for SAGMCA3 through HTTP in PEM format

## 2.3.5. External CRL Storages

### Creating a Stream External Storage

Stream allows you to push your CRLs into other Stream instances upon generation, but it requires to create an external Stream CRL storage in the product first. This section also assumes that you have already configured **Password** or **Certificate** credentials for the desired stream instance.

To configure an external Stream CRL storage:

1. Log in to the Stream Administration Interface ;

2. Go to **Revocation management** › **External CRL Storage** and click on  ;

3. Fill in the information :

- Select the **Type\*** of external CRL storage, Stream for a Stream storage
- The **Name\*** to give to that external storage
- The **Description** to add more details about this storage
- Select a list of notifications to send **On execution error** to be alerted if the push to the Stream instance fails
- Add the technical name of the **CA** you wish to push the CRL to. 3 cases can occur:
  - the technical name of the CAs are aligned on both instances: the field should be left blank, as the trigger will by default use the technical name of the CA the CRL is linked to.
  - the technical name of the CAs on the other instance can be deduced from the technical name on the current instance. A **template string** can be used to format the name correctly.
  - the technical names are not linked in any way. The technical name on the other instance

should be fully spelled out, and a trigger defined for each CA (using duplication )

- Enter the **Endpoint**\* of your other Stream instance. This should include the protocol (https://).
- Select a **Credential**\* to connect to the Stream instance. Only credentials on the **Stream** target can be selected.
- Choose a **Timeout** for the push request
- Add a **Proxy** to use to connect to the instance, if any

4. Once you've filled all the information, click "Add"

The External CRL Storage is now created and can be used in CA configuration.

## Creating an S3 External CRL Storage

Stream allows you to push your CRLs into S3 buckets upon generation, but it implies to configure an external storage first. This section also assumes you have already configured **Password** credentials for a cloud provider if you want to use a cloud storage solution.

To configure an external S3 CRL storage:

1. Log in to the Stream Administration Interface ;

2. Go to **Revocation management** › **External CRL Storage** and click on  ;

3. Fill in the information :

- Select the **Type**\* of external CRL storage, Amazon S3 for an S3 storage
- The **Name**\* to give to that external storage
- The **Description** to add more details about this storage
- Select a list of notifications to send **On execution error** to be alerted if the push to the CRL storage fails
- Add the **Bucket**\* of your S3 storage
- Select a **Credential** to connect to the S3 server (AWS format). Only credentials on the **AWS** target can be selected. If no credentials are specified, environment variable values will be used to establish connection.
- Add a **Role Arn** to use when connecting to the S3 provider (only applicable for AWS)
- Select the **Region** to use if the S3 is in the cloud (AWS, GCP)
- Add a **Proxy** to use to connect to the external storage, if any
- If not using an AWS S3 Bucket, add the S3 **Endpoint**
- Choose whether to **Force path style** in URL name
- Reconfigure the **CRL Alias**. By default, the S3 object key will be the technical name of the CA with **.crl** extension. Using **template strings**, this name can be modified. For example, if the file should be named with an uppercase of the CA's CN with the **.pem** extension, CRL Alias will be `{{ Upper({{ca.signer.dn.cn.1}}) }}.pem`

4. Once you've filled all the information, click "Add"

The External CRL Storage is now created and can be used in CA configuration.

## Creating an LDAP External Storage

Stream allows you to push your CRLs into LDAP directories upon generation, but it requires to create an external LDAP storage in the product first. This section also assumes that you have already configured **Password** credentials for the desired LDAP directory.

To configure an external LDAP CRL storage:

1. Log in to the Stream Administration Interface ;

2. Go to **Revocation management** › **External CRL Storage** and click on  ;

3. Fill in the information :

- Select the **Type\*** of external CRL storage, LDAP for an LDAP storage
- The **Name\*** to give to that external storage
- The **Description** to add more details about this storage
- Select a list of notifications to send **On execution error** to be alerted if the push to the CRL storage fails
- Add the **Host\***, IP or hostname of the LDAP server where the CRL will be pushed into. Don't add "ldap://" or "ldaps://" in the beginning
- Add the **Port\*** on which the LDAP server is running (default is 389 for LDAP and 636 for LDAPS)
- Select a **Credential\*** to connect to the LDAP server. Only credentials on the **LDAP** target can be selected.
- Add a **Proxy** to use to connect to the external storage, if any
- Enter a **Base DN\*** that points the LDAP category to publish the CRL into
- Enter a LDAP search **Filter\*** to find the resource where to publish the CRL into. **Example :** (*objectclass=cRLDistributionPoint*)
- Define the **CRL Attribute\***, the resource attribute to publish the CRL into
- Choose whether to allow Stream to **follow LDAP referral** URLs
- Choose whether to use the **Secure** LDAPS protocol instead of the regular LDAP protocol
- Choose whether to **Disable hostname validation**, allowing Stream to connect to the LDAP server in LDAPS even if the server certificate does not have the specified hostname as a DNS SAN (**only if Secure is turned on**)

4. Once you've filled all the information, click "Add"

The External CRL Storage is now created and can be used in CA configuration.

## Creating an SCP External Storage

Stream allows you to push your CRLs into any server supporting the SCP protocol upon generation. This section also assumes that you have already configured **SSH credentials** for the desired server.

To configure an external SCP CRL storage:

1. Log in to the Stream Administration Interface ;

2. Go to **Revocation management** › **External CRL Storage** and click on  ;

3. Fill in the information :

- Select the **Type\*** of external CRL storage, SCP for an SCP storage
- The **Name\*** to give to that external storage
- The **Description** to add more details about this storage
- Select a list of notifications to send **On execution error** to be alerted if the push to the CRL storage fails
- Add the **Host\***, IP or hostname of the SCP server where the CRL will be pushed into.
- Add the **Port\*** on which the SCP server is running (default is 22 for SSH)
- Select a **Credential\*** to connect to the SCP server. Only credentials on the **SCP/SFTP** target can be selected.
- Choose a **Timeout** for the SCP request
- Choose whether to **Use compression** when pushing the CRL
- Enter a known **Fingerprint** to use mutual authentication. If nothing is specified, no fingerprint check will occur.
- Define the **Path\*** where to push the CRL. Using **template strings**, this path can be dynamically set. For example, if the `crl` should be pushed to the `crls` root folder with a filename being an uppercase of the CA's CN with the `.pem` extension, path will be `/crls/{{ Upper({{ca.signer.dn.cn.1}}) }}.pem`

4. Once you've filled all the information, click "Add"

The External CRL Storage is now created and can be used in CA configuration.

## Creating an SFTP External Storage

Stream allows you to push your CRLs into any server supporting the SFTP protocol upon generation. This section also assumes that you have already configured **SSH credentials** for the desired server.

To configure an external SFTP CRL storage:

1. Log in to the Stream Administration Interface ;

2. Go to **Revocation management** › **External CRL Storage** and click on  ;

3. Fill in the information :

- Select the **Type\*** of external CRL storage, SFTP for an SFTP storage
- The **Name\*** to give to that external storage
- The **Description** to add more details about this storage
- Select a list of notifications to send **On execution error** to be alerted if the push to the CRL storage fails
- Add the **Host\***, IP or hostname of the SFTP server where the CRL will be pushed into.
- Add the **Port\*** on which the SFTP server is running (default is 22 for SSH)
- Select a **Credential\*** to connect to the SFTP server. Only credentials on the **SCP/SFTP** target can be selected.
- Choose a **Timeout** for the SFTP request
- Choose whether to **Use compression** when pushing the CRL
- Enter a known **Fingerprint** to use mutual authentication. If nothing is specified, no fingerprint check will occur.
- Define the **Path\*** where to push the CRL. Using **template strings**, this path can be dynamically set. For example, if the `crls` root folder with a filename being an uppercase of the CA's CN with the `.pem` extension, path will be `/crls/{{ Upper({{ca.signer.dn.cn.1}}) }}.pem`

4. Once you've filled all the information, click "Add"

The External CRL Storage is now created and can be used in CA configuration.

## 2.3.6. Configuring OCSP

To configure an **OCSP** responder, you first need an OCSP signer.

1. Log in to the Stream Administration Interface.

2. Go to **Revocation Management** › **OCSP Signers** and click on  at the bottom of the page.

3. Fill in the fields to create an OCSP signer that will sign OCSP requests:

- The **Name** of the OCSP signer: a technical name to identify this signer.
- The **Keystore** where to find the key for this signer.
- The **Key** that this signer will sign with.
- The **DN** of this signer, in X500 format with key=value separated by commas.
- The **Notification on signer expiration** that will notify users via Email or REST.

4. You must then generate the CSR , sign it using the CA you wish to verify certificate for, and

upload the signed certificate back to Stream [↑](#)



The certificate must be signed with the Key Usage **digitalSignature** (critical) and the Extended Key Usage **OCSPSigning**

5. The OCSP Signer is now uploaded. Additional options are now available:

- The **Response Signing Algorithm**, the hash algorithm that will be used on responses signed by this signer

6. Click the **Save** button at the bottom of the page.

Now your OCSP signer has been configured, OCSP must be enabled on a **Certification Authority**:

7. Go to **Certification Authorities**:

- **Managed CAs**, in the **CRL/OCSP** tab
- **External CAs**, in the **Configuration** tab

8. Toggle the **Enable OCSP** option. New options appear:

- **Compromised CA?** can be toggled if the CA was compromised to make all certificates on this CA act as revoked
- The **Default OCSP signer** to use if no explicit signer is defined in the OCSP request
- The **Archive Cutoff mode** to use on OCSP responses:
  - **Issuer**: the archive cutoff date will be this CA emission date
  - **Retention**: the archive cutoff date will be the OCSP request date plus the retention period

9 Click the **Save** button at the top.

## 2.4. Managing Certificate Templates & EKUs

### 2.4.1. Certificate Templates

Stream uses the notion of **Certificate Templates** to add additional verifications when enrolling a certificate.

To define a new certificate template:

1. Log in to the Stream Administration Interface.

2. Go to **Certificates > Templates** and click  .

3. In the **General** tab, you can set the template's name, the **path length** it will tolerate, turn the template on or off and check for proof of possession when enrolling with a CSR. In the **Duration** part of the tab, you can edit the lifetime of the certificates that will enroll on this template, as well as backdate them should you need to. In the **Private Key policy** part of the tab, you can choose

whether to enforce a usage period for the private key that is detached from the validity of the certificate. Should it be defined, this period must be within the validity period of the certificate. This field is optional in the RFC 5280 but mandatory in the ICAO MRTD 9303 norm (section 7.1.1) and should only be used for signature certificates.

4. In the **KU & EKU** tab, you can set the **Key Usages** and **Extended Key Usages** of the certificates that will enroll on this template. You can also use your own **EKUs** here. If you want to set up your own **EKUs**, please refer to the *Extended Key Usages* part of this section.

5. In the **Extensions** tab, you can edit the **CRLDPs**, **AIA**, **Authority Information Access**, **Policy**, **Qualified Certificate Statement** of the certificates that will enroll on this template. If you want to, the certificates could use the information of the **CA** they will enroll on, otherwise, you can set specific values in the template. These values will then override those retrieved from the CA.

- If you want to issue Qualified Certificates:
  - ETSI QC Compliance Statement declares that the certificates is a Qualified Certificate.
  - ETSI QC SSCD Statement declares that the private key related to the certified public key resides in a Secure Signature Creation Device.
  - ETSI Retention Period Statement indicates the duration of the retention period of material information.
  - ETSI QC Type Statement indicates which type of document can be signed by the certificate (possible values are: ESEAL, ESIGN, WEB, NONE).
  - ETSI Transaction Limit Statement indicates the limits of the transactions, you must fill every field if enabled.
  - ETSI QC PDS Statement is the PKI Disclosure Statement URI for a specified language.
  - ETSI QC Legislation Statement is an array of country codes.

6. In the **Data Fields** tab, you can enforce your **DNs**, **SANs** and **Extensions** to match certain criteria that can be defined in this section. By default, everything is accepted, meaning that any type and amount of **DNs**, **SANs** and **Extensions** can be used in the certificates and it would successfully enroll on the template.

- If you want to enforce a **Subject DN** policy, then click  in **Subject DN composition**, then select the DN element that you want to put a policy on. You can set this element to be mandatory or not, to use a default value for that element that can be editable or not, you can also add a whitelist of elements that are accepted values for this DN, or you can instead use a regex to match the DN values that are accepted for this element.
- If you want to enforce a **Subject Alternate Names** policy, you can either click **None** to forbid the use of **SANs** in certificates or you can click **Some** to configure the policy. If you clicked **Some**, click  and select the **SAN element** that you want to enforce a policy upon. You can then input a minimum and maximum number of this **SAN element** to be present in the certificate that will enroll: as an example, if you want to make the use of at least one **DNS SAN** mandatory, use 1 as a minimum number. Finally, you can enforce your **SANs** to match a regex to be considered valid on a certificate.

- If you want to enforce an **Extension** policy, you can either click **None** to forbid the use of **Extensions** in certificates or you can click **Some** to configure the policy. If you clicked **Some**, click  and select the **Extension** that you want to enforce a policy upon. You can then set it mandatory or not, and if supported, give it a default value that can be edited or not.

7. Once you've configured your template, you can click **Save** at the top of the page.



As mentioned previously, if you want your certificates to inherit the **CRLDP**, the **AIA** and the **Policy** from the CA, you must toggle on the **Get from CA** switches and not specify any policy, CRLDP or AIA in the template.

## 2.4.2. Extended Key Usage

Stream allows you to create and manage your own EKUs as long as you have an OID for it.

To create a custom EKU:

1. Log in to the Stream Administration Interface.
2. Go to **Certificates** > **EKU** then go at the bottom of the page and click .
3. Specify the name you want to give to your custom EKU as well as its OID in the menu, then click "Add".

The EKU should show in the list with the custom switch turned on, as opposed to the standard EKUs that have the custom switch turned off.

## 2.5. Managing Certificate Lifecycle

### Enroll



Stream's RA is not supposed to be a comprehensive registration authority and should only be used when necessary. This simple RA is made for "on the fly" generation only. If you want more advanced RA features to manually enroll certificates, you should consider using Horizon's Web RA.

To enroll a certificate via Stream:

1. Log in to the Stream Administration Interface.
2. Go to **Certificates** > **Enroll**. You'll be prompted to fill the following information:
  - **CA (select)** : The CA that will issue the certificate. The CA must be managed by Stream;
  - **Template (select)** : The Stream certificate template to use to issue the certificate;
  - **CSR type** : Whether the CSR to sign is in a dedicated file (**File** option) or in the clipboard (**Text** option);

- **CSR field** : The CSR to sign (file or PEM-string).

3. Click the **Enroll** button.

Your certificate should now be visible in the Stream search engine.

## Revoke

To revoke a certificate in Stream:

1. Log in to the Stream Administration Interface.
2. Go to **Certificates > Search** then find the certificate you want to revoke.
3. Click  on the certificate you want to revoke. Alternatively, you can click on the certificate's DN then click **Action > Revoke**.

Your certificate status should turn red.

## Search

To search for certificates in Stream, log in to the Stream Administration Interface and then go to **Certificates > Search**.

Here are all the search criteria you can use:

- **CA**: the issuing certificate authority
- **Status**: the validity status of the certificate (valid, revoked or expired)
- **Template**: the certificate template the certificate has been enrolled on
- **Certificate DNs**: information regarding the certificate's DNs
- **Expiration date**: the date when the certificate will expire
- **Issuer**: information regarding the certificate issuer's DNs
- **Serial**: the certificate's serial number

You can combine any number of them to refine your search.

## 2.6. OpenSSH

### 2.6.1. Managing Certification Authorities

1. Log in to the Stream Administration Interface.
2. Go to **OpenSSH > Certification Authority** from the menu on the left.
3. Input your CA's **internal name**.
4. Select the **Keystore** that contains the key you want to use to generate this CA, then select the key

that you want to use. If you do not have a keystore set up yet, please refer to the *Managing Keystores & Keys* section.

5. You can also configure KRL generation. To configure this section, please refer to the *Key Revocation* page. Once you're satisfied with your settings, click "Add".



OpenSSH CAs consist mainly of a keypair used to sign entity certificates and KRL, and do not expire.

## 2.6.2. Managing Key Revocation

### Configuring Key Revocation Lists for a Managed CA

To manage the **KRLs** of a managed CA, you first need to set up a **KRL Policy**:

1. Log in to the Stream Administration Interface.
2. Go to **OpenSSH > Certification Authorities** and click on  next to the name of the CA you want to edit the KRL policy of.
3. Define the validity period of your KRL, i.e. the period of time while your KRL is considered valid. The countdown starts at the moment the KRL is generated. If you want your KRLs to be valid for a week, you can type **7 days**.
4. You can then automate the **KRL generation** using either the **Hard KRL generation**, the **Lazy KRL generation** or both of them in combination:
  - The **Hard KRL generation** parameter takes a cron expression in Quartz format and generates the KRL every time that cron expression is valid, without any condition. It is recommended to generate the **KRLs** every day. To generate a new **KRL** every day at 1 A.M., the cron expression is: `0 0 1 * * ?`
  - The **Lazy KRL generation** parameter takes a cron expression in Quartz format and checks if the KRL needs to be updated, i.e. if a certificate has been revoked, since the last KRL generation. If a certificate has been revoked since the last generation then a new KRL will then be generated, otherwise it will do nothing. It is recommended to have a short time span for the lazy generation so that the KRL always stays up to date. To check for possible KRL updates every 5 minutes, the cron expression is: `0 0/5 * * * ?`
5. Click the **Save** button at the top of the page.

Now your KRL policy has been configured, and you've been redirected to the Managed CAs page.

You can then generate manually the CA's first KRL using the  button next to the CA's name that you just configured. If you configured the **Hard** or the **Lazy** generation, your KRL will then automatically be updated according to the cron quartz expression you specified.

### Viewing KRLs

1. Log in to the Stream Administration Interface.

2. Go to **OpenSSH > KRL**.

3. You can then see information regarding your CAs' KRLs that are going to be detailed below:

- The **CA** column indicates the name of the CA whose KRL is detailed in the line
- The **Number** column indicates the serial number of the KRL. It starts at 1 for the very first KRL generated and is incremented by 1 at each generation. It is displayed in hexadecimal format.
- The **Last update** column indicates the date and time when the current KRL was generated.
- The **Next refresh** column indicates the date and time when the current KRL will be refreshed. It should be equal to the nearest date matching either cron quartz expression you set in the **KRL policy** field (lazy or hard).
- The **download**  **button** allows you to download your KRL. It also serves as a KRLDP. For more information about KRLDPs in Stream, please refer to next section.
- The **generate**  **button** allows you to manually refresh the KRL and generates a new one.
- The **refresh**  **button** refreshes the information displayed in the tab, in case a generation happened in between. It **does not** refresh the KRLs, only the displayed information.

## Downloading KRLs

Stream allows you to download the **KRLs** of the **CAs** it manages. The standard download URL format is `http(s)://[stream_url]/krls/CA_internal_name`. This URL can be accessed by anyone without prior authentication, either through HTTP or HTTPS.

You need to specify the **Internal name** of the CA to download its **KRL**.

As an example, here us the **KRLDP** of a CA that were set up through this guide:

- `https://stream.evertrust.fr/krls/SAGMCA2` will download the KRL for SAGMCA2 through HTTPS in PEM format

## 2.6.3. Managing Certificate Templates

### Certificate Templates

Stream uses the notion of **Certificate Templates** to add additional verifications when enrolling a certificate.

To define a new certificate template:

1. Log in to the Stream Administration Interface.

2. Go to **OpenSSH > Templates** and click  .

3. In the **General** tab, you can set the template's name, the **type** of SSH certificates it will generate and turn the template on or off. In the **Duration** part of the tab, you can edit the lifetime of the certificates that will enroll on this template, as well as backdate them should you need to. In the **OpenSSH** part of the tab, you can edit the authorized key types as well as the principals required

on OpenSSH certificates.

4. Once you've configured your template, you can click **Save** at the top of the page.

## 2.6.4. Managing Certificate Lifecycle

### Enroll

To enroll a certificate via Stream:

1. Log in to the Stream Administration Interface.
2. Go to **OpenSSH > Enroll**. You'll be prompted to fill the following information:
  - **CA** (*select*) : The CA that will issue the certificate. The CA must be managed by Stream;
  - **Template** (*select*) : The Stream certificate template to use to issue the certificate;
  - **Public key type** : Whether the Key to sign is in a dedicated file (**File** option) or in the clipboard (**Text** option);
  - **Public key** field : The key to sign (file or PEM-string).
  - **Principals** field : The principals to sign the certificates for.
3. Click the **Enroll** button.

Your certificate should now be visible in the Stream search engine.

### Revoke

To revoke a certificate in Stream:

1. Log in to the Stream Administration Interface.
2. Go to **OpenSSH > Search** then find the certificate you want to revoke.
3. Click  on the certificate you want to revoke. Alternatively, you can click on the certificate's DN then click **Action > Revoke**.

Your certificate status should turn red.

### Search

To search for certificates in Stream, log in to the Stream Administration Interface and then go to **Certificates > Search**.

Here are all the search criteria you can use:

- **CA**: the issuing certificate authority
- **Template**: the certificate template the certificate has been enrolled on
- **Status**: the validity status of the certificate (valid, revoked or expired)

- **Valid after:** the date after which the certificate will be valid
- **Valid before:** the date when the certificate will expire
- **Key ID:** the certificate's key ID

You can combine any number of them to refine your search.

## 2.7. Managing Keystores & Keys

### 2.7.1. Keystores in Stream

In Stream, keys are grouped in key containers called **Keystores**.

Stream handles 3 types of Keystores: Software keystores, PKCS#11 HSMs and Cloud KMS. Note that some restrictions apply regarding the supported key types of the HSMs, namely:

- The software keystore supports:
  - RSA key sizes above 512 bits (the web administration console only offers RSA 2048, RSA 3072, RSA 4096 and RSA 8192);
  - 3 elliptic curves: ECC NIST P-256, ECC NIST P-384 and ECC NIST P-521;
  - 2 Edward curves: ED-448 and ED-25519;
  - 3 MLDSA Algorithms: MLDSA-44, MLDSA-65 and MLDSA-87;
  - 3 MLDSA Algorithms with PreHash: MLDSA-44 + SHA512, MLDSA-65 + SHA512 and MLDSA-87 + SHA512;
- The PKCS#11 keystore crypto capabilities are entirely reliant on the HSM that is used. Generally, RSA keys are all supported, while elliptic curves are not all supported by every HSM vendor. Currently, Edward curves are also not supported by some HSM vendors; PQC is not yet standardized in PKCS#11 so MLDSA support is not yet available.
- Stream can consume the following key types from an AWS KMS instance:
  - RSA 2048, RSA 3072, RSA 4096;
  - ECC NIST P-256, ECC NIST P-384, ECC NIST P-521;
  - The AWS KMS currently does not support Edward Curves;
  - Stream currently does not support the ECC SECG P-256k1;
- Stream can consume the following key types from an AKV instance:
  - RSA 2048, RSA 3072, RSA 4096;
  - ECC NIST P-256, ECC NIST P-384, ECC NIST P-521;
  - Azure Key Vaults (even the Premium ones) currently do not support Edward Curves;
  - Stream currently does not support the ECC SECG P-256k1;
- Stream can consume the following key types from a GCP CKM instance:
  - RSA 2048, RSA 3072, RSA 4096;
  - ECC NIST P-256 and ECC NIST P-384;

- The GCP CKM currently does not support Edward Curves.

## 2.7.2. Software keystore

Stream comes installed with a software keystore that can be used to generate RSA and ECDSA keys. To set up a software keystore:

1. Log in to the Stream Administration Interface.
2. Go to **Keystores and keys** and click .
3. In **Type**, select **Software**. In **Name**, set the name you want to give to your keystore. Optionally, you can add a description to your keystore.
4. Click the **Add** button.

Your keystore should appear in your keystores list with a green circle next to its name.



When using the software keystore, private keys are at some point stored in memory in **plain text**. That represents a huge security flaw since it would just take a memory dump of the Stream machine to be able to recover the private keys.



It is **not recommended** to use the software keystore except for testing or development purposes due to the safety reasons detailed above.

## 2.7.3. PKCS#11 HSM

Stream supports key management through **PKCS#11 HSMs**.

Stream has been qualified to work with the following **HSMs** but should be working with any **PKCS#11 HSM**:

- Entrust nShield Solo, Entrust nShield Connect, Entrust nShield as a Service
- Atos Proteccio
- Thales Luna (including DPoD), Thales Protect Server
- Utimaco CryptoServer

To set up a PKCS#11 keystore:

1. Log in to the Stream Administration Interface.
2. Go to **Keystores and keys** and click .
3. In **Type**, select **PKCS#11**. In **Name**, set the name you want to give to your keystore. Optionally, you can add a description to your keystore.
4. Input the **full path** of the **PKCS#11 library** (ending in `.so`) of your HSM, then click the parse .

button. If your HSM's library was successfully loaded into Stream, you should be seeing your HSM's information. If you get an HSM error, please check the configuration of your HSM. Click "Next".

5. Select the **HSM slot** that you will be using on your HSM for this keystore and input its **PIN code**;
6. Optionally, you can set a Pool Size to your PKCS#11 interface. If disabled, Stream will open a PKCS#11 session every time it needs to sign a certificate, then close it afterwards. If enabled, Stream will open the number of connections specified in the pool size value and maintain them open as long as Stream is running, to be able to directly sign certificates without having to open a PKCS#11 session. This feature comes particularly handy whenever working with a slow HSM, where opening a session is a pretty long operation that can completely ruin performance.

Once you are done, click "Save". Your keystore should appear in your keystores list with a green circle next to its name.

## 2.7.4. Cloud KMS

Stream supports 3 types of Cloud KMS: Google Cloud Platform (GCP), AWS Key Management Service (KMS) and Microsoft Azure Key Vault (AKV).

### Setting up a Google Cloud Key Management (GCP CKM)

1. Log in to the Stream Administration Interface.
2. Go to **Keystores and keys** and click  .
3. In **Type**, select **Google Cloud Platform**. In **Name**, set the name you want to give to your keystore. Optionally, you can add a description to your keystore.
4. Select the GCP credential to use to connect to the Cloud Key Management service. If you do not have your GCP CKM credentials set up in Stream yet, please refer to the *Credentials* part of the *Managing Security* section.
5. Input the **GCP Project name** in **Project**, the **GCP Server location** to use and the **GCP Key Ring** to use. Additionally, you can specify the **proxy** to use as well as the **timeout period**. Once you are done, click "Add".

Your keystore should appear in your keystores list with a green circle next to its name.

### Setting up an AWS Key Management Service (AWS KMS)

1. Log in to the Stream Administration Interface.
2. Go to **Keystores and keys** and click  .
3. In **Type**, select **AWS**. In **Name**, set the name you want to give to your keystore. Optionally, you can add a description to your keystore.
4. Select the AWS credential to use to connect to the AWS Key Management Service. If you do not

have your AWS KMS credentials set up in Stream yet, please refer to the *Credentials* part of the *Managing Security* section.

5. Input the **AWS server's region** in **AWS Region**. Optionally, you can specify which AWS Role ARN that should be impersonated for that KMS. Additionally, you can specify the **proxy** to use as well as the **timeout period**. Once you are done, click "Add".



To make Stream able to use the keys in the AWS KMS for signature, you need to give it the proper permissions in the AWS console. For more information regarding this topic, please refer to [this link](#), under the "Asymmetric KMS keys for signing and verification".

Your keystore should appear in your keystores list with a green circle next to its name.

## Microsoft Azure Key Vault (AKV)

1. Log in to the Stream Administration Interface.

2. Go to **Keystores and keys** and click  .

3. In **Type**, select **Azure Key Vault**. In **Name**, set the name you want to give to your keystore. Optionally, you can add a description to your keystore.

4. Select the AKV credential to use to connect to the Microsoft Azure Key Vault. If you do not have your Microsoft AKV credentials set up in Stream yet, please refer to the *Credentials* part of the *Managing Security* section.

5. Specify your Azure vault URL in the **Vault URL** box and the Azure tenant in the **Azure Tenant** box. Additionally, you can specify the **proxy** to use as well as the **timeout period**. Once you are done, click "Add".

Your keystore should appear in your keystores list with a green circle next to its name.

## 2.7.5. Managing keys in Stream

Regardless of the type of keystores you set up, you can manage the keys through Stream the same way

### Adding a key into a keystore

1. Log in to the Stream Administration Interface.

2. Go to **Keystores and keys** and click  on the keystore you want to add the key into.

3. Set the name of the key as well as the key type (RSA, ECDSA or EDDSA) and the key size (for RSA)/key parameter (for ECDSA/EDDSA).

4. For the **Cloud KMSs**, you can set the key to be **Hardware protected** through the dedicated toggle. For the **PKCS#11 HSM**, you can set the key to be **exportable** through the dedicated toggle.

5. Once you set up the key parameters as you want them, click "Add".

The page should refresh and show you the list of keys for the keystore you pushed the key into, where you should see the key you just added.

## Viewing the keys of a keystore

1. Log in to the Stream Administration Interface.
2. Go to **Keystores and keys** and click  on the keystore you want to view.
3. You should see the list of keys on your keystore.

You can then see information about the keys in the keystore:

- The **name** column where you can see the name of the key ;
- The **type** column where you can see the type of algorithm that was used to generate the key. Both RSA and ECDSA are part of the *suiteb* type algorithms ;
- The **key type** column where you can see the algorithm that was used to generate the key as well as the key size/parameter ;
- The **exportable** column indicates if the key is exportable or not.

## Deleting a key from a keystore

1. Log in to the Stream Administration Interface.
2. Go to **Keystores and keys** and click  on the keystore you want to delete the key from.
3. Click the  icon on the key that you want to delete and click "Confirm" on the prompt.



You cannot delete a key from a keystore if this key is currently used by a CA in Stream. You must first delete the CA that references it and then go over the deleting procedure.

## 2.8. Managing Notifications

### 2.8.1. Email

*This section details how to configure the email notifications.*

#### How to create an email notification

1. Log in to Stream Administration Interface.
2. Access emails from the drawer or card: **Notifications** › **Emails**.
3. Click on  .

#### 4. Fill in all mandatory fields in the Notifications details panel.

- The **Name** of the notification.
- The **Lifecycle event** triggering the notification.
  - First, select the entity **Type** can be one of:
    - CA: events on the Certification Authority lifecycle, like expiration of a CA
    - CRL: events on the CRL lifecycle, like a generation or update
    - OCSP Signer: events on the OCSP Signers lifecycle, like expiration of an OCSP signer
    - System: events concerning Stream global objects, like credentials or license expiration
    - Timestamping Signer: events on the Timestamping Signers lifecycle, like expiration of a Timestamping signer
  - Then, select the **Event** you wish to send the notification on.
- Select the notifications to send **On execution error** of this Notification to be alerted if it failed.
- The **Delay before notification sending** is only enabled when the **Event** is about the expiration of an entity. This is the period where the notification will be sent before the expiration date.

#### 5. Fill in all mandatory fields in the Notifications Email details panel.

- The email sender **From** which the mail will be sent.
- The email targets **To** send email.
- The email **Subject**, a **template string** that will be dynamically evaluated upon email generation.
- The email **Body**, a **template string** that will be dynamically evaluated upon email generation.
- Set whether the email body **is HTML**. The default value is set to false.



You can click on the  next to the "Dynamic attributes" section, in order to get a range of possibilities on which **dictionaries** and **functions** are available.

#### 6. Click on the save button.

You can edit , duplicate  or delete  the Email Notification.

## 2.8.2. REST

This section details how to configure REST notifications.

### How to create a REST notification

1. Log in to Horizon Administration Interface.

2. Access REST from the drawer or card: **Notifications** › **REST**.

3. Click on .

4. Fill in all mandatory fields in the Notifications details panel.

- The **Name** of the notification.
- The **Lifecycle event** triggering the notification.
  - First, select the entity **Type** can be one of:
    - CA: events on the Certification Authority lifecycle, like expiration of a CA
    - CRL: events on the CRL lifecycle, like a generation or update
    - OCSP Signer: events on the OCSP Signers lifecycle, like expiration of an OCSP signer
    - System: events concerning Stream global objects, like credentials or license expiration
    - Timestamping Signer: events on the Timestamping Signers lifecycle, like expiration of a Timestamping signer
  - Then, select the **Event** you wish to send the notification on.
- Select the notifications to send **On execution error** of this Notification to be alerted if it failed.
- The **Delay before notification sending** is only enabled when the **Event** is about the expiration of an entity. This is the period where the notification will be sent before the expiration date.

5. Fill in all mandatory fields in the Notifications Rest details panel.

- The REST **HTTP method and URL** that the HTTP request will use
- The **Proxy** used by Stream to send the HTTP request.
- The **Timeout** to wait before stopping listening to an answer.
- The **Accepted response HTTP code(s)** to consider the request in success state.
- The **Authentication type and credentials** used by the HTTP request, for example, the basic authentication.
- The **Headers** sent along with the HTTP request. Each header value is a **template string** that will be dynamically evaluated when sending the notification.
- The **Payload** of the HTTP request. It is a **template string** that will be dynamically evaluated when sending the notification.



You can click on the  next to the "Dynamic attributes" section, in order to get a

range of possibilities on which dictionaries and functions are available.

6. Click on the save button.

You can edit , duplicate  or delete  the Email Notification.

## 2.9. Managing Security

### 2.9.1. Authorizations

*This section details how to configure the permissions granted to an account, either directly or through a configured role.*

#### Prerequisites

According to the context, you might need to set up:

- [admin-guide:security-roles::\_roles]
- Local accounts

#### How to add an authorization manually or from a certificate

1. Log in to Stream Administration Interface.

2. Access Authorizations from the drawer or card: **Security** › **Authorizations**.

3. Click on .

4. Click on  Add Authorization Manually

5. Fill the mandatory fields:

- Either:
  - Fill in an **Identifier**\*: it can be either a local account identifier or an OpenID Connect identifier (usually email address).
  - Import a certificate by clicking on certificate button .

6. Click on add button.

#### How to add an authorization from a search

1. Log in to Stream Administration Interface.

2. Access Authorizations from the drawer or card: **Security** › **Authorizations**.

3. Click on .

4. Click on  Search and Add Authorization

5. Search by **Identifier** for a local account previously defined.

6. Click on search button.

7. Choose the identifier you want to add.

8. Click on add button.

You can update , see connexion information , or delete  Authorization.

## How to grant a permission

1. Click on .

### Role

2. Select a role previously created (if needed).

### Permissions

Stream allows you to manage 2 types of permissions: configuration and lifecycle.

Stream uses wildcard permissions which means you can configure the permissions very thoroughly.

### Configuration

For configuration permissions, you can specify:

- the **Section** (ex: Security)
- the concerned **Module** (only for select modules)
- the type of permission: **Audit** (read-only) or **Manage** (read-write, equivalent to *All*).

4. Click on add button.

5. Select a section, then a module, then a submodule if there is, and a right.

6. Click on add button (Don't forget to save).

7. Click on the save button if you are done.

### Lifecycle

For lifecycle permissions, you can specify the concerned **CA** and the concerned **Template** then the type of permission: **Enroll**, **Revoke**, **Search** or **All** of these.

4. Click on add button.

5. Select a module, then a profile, and a right.

6. Click on add button. (don't forget to save).

7. Click on the save button if you are done.

## 2.9.2. Credentials

This section details how to configure credentials. Credentials are where credentials for all integrations are regrouped.

### How to create credentials

1. Log in to Stream Administration Interface.

2. Access Credentials from the drawer or card: **Security** > **Credentials**.

3. Click on .

4. Fill the fields.

- The **Type\***: **Certificate** for certificate based authentication, **Login** for login with password credentials, **API Token** for a single value secret (JSON or other) or **SSH** for SSH Keys secret.
- The **Name\*** of the credentials. It should clearly identify it.
- The **Description** to add additional information on these credentials.
- The **Expiration date**. This will be taken from the certificate for **Certificate** credentials, and will be used for notifications on expiration.
- The **Expiration notifications** are `[admin-guide:notifications-mail::_email]` or `[admin-guide:notifications-rest::_REST]` notifications on event **Credentials expiration** that will run on expiration. Notifications configured here will be sent by the internal monitoring action.
- Certificate:
  - The **PKCS#12\*** file containing the authentication certificate and its key.
  - The **PKCS#12 Password\*** to open this PKCS#12.
- Credentials:
  - The **Login\*** of the account.
  - The **Password\*** of the account.
- API Token:
  - The **API Token\*** to use.
- SSH:
  - The **SSH identifier\***: username to use for SSH connection.
  - The **SSH key\*** is the SSH private key in OpenSSH format for SSH connection.

5. Click on the save button.

You can update  or delete  the Credentials.

## 2.9.3. Identity Providers

## How to configure an Identity Provider

1. Log in to Stream Administration Interface.
2. Access Identity Providers from the drawer or card: **Security** › **Access Management** › **Identity Providers**.
3. Click on .

### General tab

4. Select an identity provider type. Currently only OpenID is supported

### OpenID connect

5. Fill in all fields:
  - The **Name**\* will be used to identify this provider on Stream and on the login page.
  - **Enabled**\* allows to disable the identity provider when access from this authentication source is not needed.
  - **Enabled on UI**\* allows to hide this provider on the login page, but it will still be available via direct API calls.
  - The **Provider metadata URL**\* is the url where the OIDC provider provides its metadata. For example `https://<oidc server>/well-known/openid-configuration`.
  - The **Client Credentials**\* are **Password** credentials containing the client id and secret used to connect to the OIDC provider. They can be created on the go using the .
  - The **Scope**\* used by Stream during authentication on the identity provider to authorize access to user's details.
  - The **Proxy** used to access Provider metadata URL, if any.
  - The **Timeout** used for authentication on the identity provider. Must be a valid finite duration. The default value is 10 seconds.
  - The **Identifier Claim**\* is a **template string** defining how to construct the identifier from the OpenID Connect claims. For example, if the user identifier is contained in the **login** claim, and should be lower case, then the configured value should be `{{Lower({{login}})}`.
  - The **Name Claim**\* is a **template string** defining how to construct the user name from the OpenID Connect claims. For example, if the user name must be constructed as **family name**, **GIVEN NAME** and family name is available in the **family\_name** claim, given name is available in the **given\_name** claim, then the configured value should be `{{family_name}}, {{Upper({{given_name}})}`
6. Click on the save button.

You can update  or delete  the Identity Provider.



You won't be able to delete an Identity Provider if it is referenced in any other

configuration element.

## 2.9.4. Local Accounts

### How to create local accounts

1. Log in to Stream Administration Interface.
2. Access Local accounts from the drawer or card: **Security** › **Access Management** › **Local Accounts**.
3. Click on  .
4. Fill in the fields:
  - The **Identifier\***, a meaningful identifier for the account holder. It will be used as a login to access to the solution.
  - The **Name\*** for the account holder. It will be displayed on the interface when logged in.
5. Click on the create button. The account is created and a password is generated.

### How to reset a password on a local account

1. Once a local account is created. Click on .

You can edit  or delete  a local account. You can reset  a local account password.



You can not delete yourself from local accounts.

## 2.9.5. Roles

Roles are a way to factor permissions making it easier to configure accounts and track permissions.

### Creating a new role

1. Log in to the Stream Administration Interface.
2. Go to **Security** > **Roles** and click  ;
3. Set the **name** of the role you want to create. Optionally, you can add a **description** to the role.
4. Add the **configuration permissions** you want the members of this role to have using the  from **Configuration permissions**. If the role is supposed to have no configuration permission, leave this section empty.
5. Add the **lifecycle permissions** you want the members of this role to have using the  from

**Lifecycle permissions.** If the role is supposed to have no lifecycle permission, leave this section empty.

Once everything is set up, you can click **Save**.

## Managing roles

1. Log in to the Stream Administration Interface.

2. Go to **Security > Accounts**. From there, you can see all Stream roles and their associated information.

- The **name** column displays the role's name;
- The **description** column displays the role's description;
- The **permissions** column shows the **straight permissions** that are set up for the role. If the account has any **configuration** permission, it will display  and if it has any lifecycle permission it will display .
- You can **view all the members of a role** using the  button;
- You can **delete a role** using the  button;
- You can **edit a role's** information using the  button.

### 2.9.6. Enforce Certificate Authentication

It is possible to enable `x509_enforcing` parameter in order to authorize only certificate authentication.



This means local accounts will no longer be able to connect on Stream.



When logging in using an X509 certificate, there is no logout option, meaning that the only way to log out is to change the presented certificate in your browser, or to switch to private browsing.

## Using Stream configuration utility

Connect to the server with an account with administrative privileges;

Start the Stream configuration utility by running:

```
# /opt/stream/sbin/stream-config
```

In the main menu, select '**Stream**':

```
EverTrust Stream Configuration Utility
+-----+
| SMTP      | Configure SMTP relay
| Administrator | Configure Stream Administrator's Email
| Akka_Play | Configure Akka and Play for EverTrust Stream
| Stream    | Configure EverTrust Stream
| NGINX     | Configure Local NGINX and External Front-End Support
| EXIT      | Exit Configuration Utility
+-----+
| < DK >   | <Cancel>
+-----+
```

In the Stream menu, select 'STREAM\_ENFORCE\_X509':

```
EverTrust Stream Settings
+-----+
| JVM       | Configure JVM Parameters
| STREAM_LOGLEVEL | Configure Stream Log Level
| STREAM_LICENSE | Import a license file
| MONGODB_URI | Configure MongoDB URI
| STREAM_HOSTNAME | Configure Stream Hostname
| STREAM_SEAL_SECRET | Configure the events seal secret
| STREAM_TINK_KEYSET | Configure the stream keyset
| STREAM_ENFORCE_X509 | Configure the enforcing of certificate authentication
| EXIT      | Exit Configuration
+-----+
| < DK >   | <Cancel>
+-----+
```

In the X509 Authentication Enforcing menu, select 'ENABLE':

```
X509 Authentication enforcing
If enabled, Stream will only allow certificate authentication
If disabled, Stream will allow all authentication modes
+-----+
| ( ) ENABLE | Enable x509 authentication enforcing
| (*) DISABLE | Disable x509 authentication enforcing
+-----+
| < DK >   | <Cancel>
+-----+
```

For the changes to take effect, you must restart the Stream service by running:

```
# systemctl restart stream
```

X509 Authentication is now enforced.

## Re-enable local authentication




This should be done in a confined and secure environment.

If you lose all available authentication certificates to Stream and want to re-gain access to the administration console, please follow these steps:

Connect to the server with an account with administrative privileges;

Start the Stream configuration utility by running:


```
# /opt/stream/sbin/stream-config
```



In the Stream menu, select '**STREAM\_ENFORCE\_X509**':



In the X509 Authentication Enforcing menu, select '**DISABLE**':



For the changes to take effect, you must restart the Stream service by running:

```
# systemctl restart stream
```

Now that the X509 enforcing is disabled, you can log in with the initial administrator account that was created during the bootstrap of the product. If you lost access to that account as well, or if you deleted it, please contact the EVERTRUST support.

## 2.10. Managing Stream instance

### 2.10.1. Events

The event system exists to overview the actions happening on Stream.

By default, the events are chained by the following rule: event  $n$  references event  $n-1$ . They are signed with the event seal secret set up during the stream installation.

To consult them:

1. Log in to the Stream Administration Interface.
2. Go to **System** > **Events**.

### Event integrity reports

To check the integrity of the events, you can run an event integrity report:

1. Log in to the Stream Administration Interface.
2. Go to **System** > **Events Integrity Reports**.
3. Click ;
4. Click **Run**

The integrity of the event chain is checked and can take some time depending on the number of events in the database. Once finished, the report may have different status:

- **Running**: the integrity of the events is currently being checked.
- **Verified**: the event chain is not compromised.
- **Report integrity failure**: the report signature has been compromised.
- **Event integrity failure**: the event chain has been compromised, one event could have been modified or deleted. The event integrity report error provides details about the cause of the integrity failure.



Any compromised object means an account with enough permission to write in the database has been compromised.

## Purging/Backup event database



Manual actions regarding the events manipulation should be done with stream turned off and in a confined environment.


Follow the Backup guide to save your database. Once done, you might want to delete the events in database.

Deletion of events can only be made from the oldest to the newest since events are chained. For example, you might want to delete every event before a date:


```
use stream;
db.events.deleteMany({"timestamp":{"$lt: ISODate("2023-09-20")}});
```

After the deletion of events, the Head is still chained to a deleted event. In order to fix that, you will need to run the **Set the first event as head** in `/opt/stream/sbin/stream-config`:

In the main menu, select '**Stream**':



In the Stream menu, select '**STREAM\_EVENT\_SET\_HEAD**':



## Integrity compromised

If an event or event integrity report has been compromised, it means that someone had database access to Stream or one of its backups and manually edited the events to hide specific actions.

You should close all network access to the server and, if necessary, turn off stream. Once confined, you should follow these steps:

1. Follow the [Backup guide](#) to back up your database. It may be used to investigate the problem.
2. Analyze the logs (you may use an older verified backup to assess modifications).



Since the database has been compromised, every event should be considered as a non trusted information

3. Based on your assessments, take the appropriate actions. This could mean changing the mongod password, changing the server password, revoking stream access certificates or other actions.
4. To resume a normal state, remove every corrupted event following the steps in the [event purge guide](#).

## 2.10.2. Event codes documentation

All the events displayed in this document work in a similar manner. In case of a failure, the event will display the reason of said failure. This behavior is also valid for warning-status events.

### BOOTSTRAP

Bootstrap events relate to the initial setup of the Stream platform.

- **BOOTSTRAP-ADMINISTRATOR-ACCOUNT**  
This event is triggered when installing Stream, it corresponds to the creation of the administrator local identity on Stream.
- **BOOTSTRAP-ADMINISTRATOR-PRINCIPAL**  
This event is triggered when installing Stream, it corresponds to the creation of a link between the administrator account and its rights.
- **BOOTSTRAP-LOCAL-IDENTITY-PROVIDER**  
This event is triggered when installing Stream, it corresponds to the creation of a provider of type Local so that the administrator can connect after startup.
- **BOOTSTRAP-SYSTEM-CONFIGURATION**  
This event is triggered when installing Stream, it corresponds to the creation of internal configuration elements such as the CRON internal monitor.

### CA

- **CA-CRL-GEN**  
This event occurs on a CRL Generation request on a CA.
- **CA-CRL-UPLOAD**  
This event occurs when a CRL is being uploaded on a CA.
- **CA-CSR**  
This event occurs when a CSR generation is requested on a CA. This is commonly part of the CA issuing process.
- **CA-ENHANCE**  
This event occurs when a legacy CA is being enhanced to a PQC-ready CA.

- **CA-ISSUE**  
This event occurs when a CA is being issued.
- **CA-KRL-GEN**  
This event occurs on a KRL Generation request on a CA.
- **CA-MIGRATE**  
This event occurs when an external CA is being migrated to a managed CA.
- **CA-REVOKE**  
This event occurs on a CA revocation attempt.

## CONF

*CONF* events are triggered when users interact with configuration elements. This includes certificate templates, notification triggers, Certification Authorities...

- **CONF-ADD**  
This event is triggered when a user tries to add a configuration element.
- **CONF-DELETE**  
This event is triggered when a user tries to delete a configuration element.
- **CONF-UPDATE**  
This event occurs when a user tries to modify a configuration element.

## CRL

- **CRL-GEN**  
This event occurs on a CRL generation attempt, either requested by application processes or the user.
- **CRL-GET**  
This event occurs on a CRL retrieval attempt from a CRLDP. These are attempted by the application.
- **CRL-SYNC**  
This event is triggered when a failure occurs on a CRL Synchronization.
- **CRL-UPLOAD**  
This event occurs when a user tries to upload a new CRL on a CA.

## EVENT COMPLIANCE

- **INVALID-SEAL-PENDING-EVENT**  
This event occurs when a pending event has an invalid seal (indicating data corruption in the pending events collection).
- **UNSEALED-PENDING-EVENT**  
This event occurs when a pending event has no seal (indicating data corruption in the pending events collection).

## INTERNAL MONITOR

- **INTERNAL-MONITOR-INIT**

This event occurs when a bad initialization of the internal monitor happens. It is a failure case, happening for instance when it is not configured

- **INTERNAL-MONITOR-RUN**

This event occurs when the internal monitor completes successfully.

## KRL

- **KRL-GEN**

This event occurs on a KRL generation attempt, either requested by application processes or the user.

- **KRL-SYNC**

This event is triggered when a failure occurs on a KRL Synchronization.

## LICENSE

- **LICENSE-EXPIRED**

This event occurs when the license has expired.

- **LICENSE-INVALID**

This event occurs when the license contains no entitled modules.

- **LICENSE-MODULE-NOT-ENTITLED**

This event occurs when the requested module is not entitled on the license.

## LIFECYCLE

- **LIFECYCLE-ENROLL**

This event is triggered when an enrollment request for an end-entity certificate is received. The event specifies all the requested certificate fields, as well as CA, keystore and template information. In case of success, the issued certificate PEM is specified. In case of failure, the reason of the failure is specified (e.g.: "Unauthorized DN element").

- **LIFECYCLE-REVOKE**

This event occurs when a user tries to revoke a certificate. Note that no event is triggered when a certificate expires.

## OCSP

- **OCSP-CSR**

This event is triggered when issuing a CSR for an OCSP Signer.

## SECURITY

- **BOOTSTRAP-ADMINISTRATOR**

This event is triggered when installing Stream, it corresponds to the creation of the initial administrator account (replaced by **BOOTSTRAP-ADMINISTRATOR-PRINCIPAL** & **BOOTSTRAP-**

ADMINISTRATOR-ACCOUNT).



Deprecated since version 2.0.0

- **SEC-AUTHENTICATION**

This event is triggered when a user tries to connect. The identifier (local, OpenID, X509 DN, ...) is specified whether it is a failure or a success.

## ACCOUNT

- **SEC-ACCOUNT-ADD**

This event occurs when an account is created (replaced by authorizations & local accounts).



Deprecated since version 2.0.0

- **SEC-ACCOUNT-DELETE**

This event occurs when an account is deleted (replaced by authorizations & local accounts).



Deprecated since version 2.0.0

- **SEC-ACCOUNT-UPDATE**

This event occurs when an account is updated (replaced by authorizations & local accounts).



Deprecated since version 2.0.0

## AUTHORIZATION



These events relate to the Security>Access Management>Authorizations tab under configuration.

- **SEC-AUTHORIZATION-ADD**

This event is triggered when a user tries to create a an authorization object.

- **SEC-AUTHORIZATION-DELETE**

This event is triggered when a user tries to delete an authorization object.

- **SEC-AUTHORIZATION-UPDATE**

This event is triggered when a user tries to modify elements inside an authorization object. The event specifies the modified fields.

## CREDENTIALS



These events relate to the Security>Credentials tab under configuration.

- **SEC-CREDENTIAL-ADD**

This event occurs when a user tries creating new credentials.

- **SEC-CREDENTIAL-DELETE**

This event occurs when a user tries deleting credentials.

- **SEC-CREDENTIAL-UPDATE**

This event occurs when a user tries updating credentials.

## IDENTITY



These events relate to the Security>Access Management>Identity tab under configuration.

- **SEC-IDENTITY-PROVIDER-ADD**

This event occurs when a user tries creating an identity provider profile.

- **SEC-IDENTITY-PROVIDER-DELETE**

This event occurs when a user tries deleting an identity provider profile.

- **SEC-IDENTITY-PROVIDER-UPDATE**

This event occurs when a user tries modifying an identity provider profile. The modified fields are specified in the event.

## LOCAL IDENTITY



These events relate to the Security>Access Management>Local accounts tab under configuration.

- **SEC-LOCAL-IDENTITY-ADD**

This event is triggered when a user tries creating a local account.

- **SEC-LOCAL-IDENTITY-DELETE**

This event is triggered when a user tries to delete a local account.

- **SEC-LOCAL-IDENTITY-RESET**

This event is triggered when executing the reset password workflow.

- **SEC-LOCAL-IDENTITY-UPDATE**

This event is triggered when a user tries modifying a local account. The modified fields are specified. Updating the password falls in this event.

## ROLE



These events relate to the Security>Access Management>Roles tab under configuration.

- **SEC-ROLE-ADD**

This event is triggered when a user tries to create a new role.

- **SEC-ROLE-DELETE**

This event is triggered when a user tries to delete a role.

- **SEC-ROLE-UPDATE**

This event is triggered when a user tries to modify a role. The modified fields are specified in the event.

## SERVICE

- **SERVICE-START**

This event is triggered when the Stream service is started.

- **SERVICE-STOP**

This event is triggered when the Stream service is manually stopped.

## TIMESTAMPING

- **TSA-CSR**

This event is triggered when issuing a CSR for a Timestamping Signer.

## TRIGGER

- **CRL-EXTERNAL-STORAGE**

This event is triggered when a CRL External Storage runs (replaced by TRIGGER-RUN).



Deprecated since version 2.0.0

- **TRIGGER-RUN**

This event occurs when a trigger (External CRL/KRL Storage, Notification) runs.

## 2.10.3. Proxies

### How to configure an HTTP Proxy

1. Log in to Stream Administration Interface.
2. Access HTTP Proxy from the drawer or card: **System** > **HTTP Proxies**.
3. Click on  .
4. Fill the fields:
  - The **Name**\* of the proxy.
  - The **Host**\* is the Hostname or IP Address of the proxy.
  - The **Port**\* of the proxy.
5. Click on the create button to save.

You can update  or delete  the HTTP Proxy.



You won't be able to delete an HTTP Proxy if it is referenced in any other configuration element.

## 2.10.4. Queue

### Queue Configuration

1. Log in to Stream Administration Interface.

2. Access Queues from the drawer or card: **System** › **Queues**.

3. Click on  .

4. Fill in the fields:

- The **Name**\* of the queue. It must be unique.
- The **Description** to add additional information on this queue.
- The **Throttle Duration** and **Throttle Parallelism**. The maximum number of **parallel** request during the **duration**.
- The **Max Size**\* of the queue



If the queue is full every new request will be discarded.

- The **Cluster Wide** parameter defines the queue behavior in multi node setup. If not enabled, then the `throttleParallelism` and `throttleDuration` will be the same for all nodes in the cluster. If enabled, then the `throttleParallelism` and `throttleDuration` is generalized for all clusters.

## 2.10.5. Global configuration

These configurations handle various Stream global parameters directly via the Web Interface.

### Internal monitoring

This parameter configures the internal monitoring execution interval. Internal monitoring refers to an action that will check the expiration and usage status of credentials and license, and send the configured notifications if needed.

By default, this action will be executed every day at midnight UTC. The notifications will keep being sent each day for as long as an action is needed.

### License configuration

The license configuration panel allows to configure `[admin-guide:notifications-mail::_email]` or `[admin-guide:notifications-rest::_REST]` notifications to be sent on license expiration: using a notification on the `License Expiration` event and the `Delay before notification sending` field in the notification configuration, notifications configured here will be sent by the internal monitoring action.

## 2.11. Timestamping

### 2.11.1. Timestamping Authorities

To configure a Timestamping Authority, a Timestamping Signer and an NTP Client(s) must already be configured.

1. Log in to the Stream Administration Interface.
2. Go to **Timestamping** › **Authorities** and click on  at the bottom of the page.
3. Fill the fields:
  - The unique **Name**\* of the Timestamping Authority
  - Choose whether to **Enable** it to sign timestamping requests
  - Enter the **Policy OID**\* this authority manages
  - Add a **Timestamping Signer**\* that will sign the requests for this authority
  - Select the **Accepted Hash Algorithms**\* for signature
  - Select the **NTP Client(s)**\* that will be the time source for the timestamping
  - Choose whether to **Check Revocation** of the signer certificate when processing timestamping requests
4. Click "Save" at the bottom.

If everything was ok, the authority now appears in the list.

### 2.11.2. NTP Clients

1. Log in to the Stream Administration Interface.
2. Go to **Timestamping** › **NTP** and click on  at the bottom of the page.
3. Fill the fields:
  - The unique **Name**\* of the NTP client
  - Enter a **Description** for additional information about this NTP Client
  - Enter the **Host**\* where to find the NTP server
  - Enter the **Port** where to join the NTP server on. Default is the standard 123 port.
  - Select a **Timeout**\* for NTP requests
  - Choose the NTP parameters like the **Max Stratum**, defining the maximum authorized stratum, the **Max Offset**, defining the maximum offset allowed between local system clock and NTP clock and **Max RTT**, the maximum round trip time allowed.
4. Click "Save" at the bottom.

After these steps, the NTP client now appears in the list.

### 2.11.3. Timestamping Signers

1. Log in to the Stream Administration Interface.
2. Go to **Timestamping** › **Signers** and click on  at the bottom of the page.
3. Fill in the fields to create a Timestamping signer that will sign Timestamping requests:
  - The **Name** of the Timestamping signer: a technical name to identify this signer.
  - The **Keystore** where to find the key for this signer.
  - The **Key** that this signer will sign with.
  - The **DN** of this signer, in X500 format with key=value separated by commas.
  - The **Notification on signer expiration** that will notify users via **Email** or **REST**.
4. You must then generate the CSR , sign it using your Timestamping CA, and upload the signed certificate back to Stream .



The certificate must be signed with the Key Usage **digitalSignature** (critical) and the Extended Key Usage **timeStamping** (critical)

5. The Timestamping Signer is now uploaded. Additional options are now available:
  - The **Response Signing Algorithm**, the hash algorithm that will be used on responses signed by this signer
6. Click the **Save** button at the bottom of the page.

## 2.12. Backup and Restore

This section details how to use the provided EverTrust Tools to back-up and restore Stream if deployed using the RPM package. If you deployed Stream using Docker/Kubernetes, the configuration should be backed-up using the Docker/Kubernetes management platform, and the database should be backed-up using MongoDB tools.

### Backup Procedure

This section details how to back up Stream configuration elements (the /opt/stream/etc folder, that includes the Nginx configuration, and the /etc/default/stream configuration file) and the Stream MongoDB database.

The backup tool allows backing up these elements independently.

```
# /opt/stream/sbin/stream-backup --help
```

Stream Backup tool usage: `stream-backup [-cdeho:q]`

`-c` | `--conf` Backup the Stream configuration files

`-d` | `--db` Backup the Stream MongoDB Database

`-e` | `--encrypt` Encrypt the backup files with the specified passphrase

`-h` | `--help` Display the 'stream-backup' help

`-o` | `--output` [path] Specify the Stream backup output folder (default: '/opt/stream/var/backup')

`-q` | `--quiet` Quiet mode

To back up the configuration files, run the following command:

```
# /opt/stream/sbin/stream-backup -c
```

The configuration files backup consists of a compressed archive (`.tar.gz`) located under `/opt/stream/var/backup/`.

To back up the MongoDB database, run the following command:

```
# /opt/stream/sbin/stream-backup -d
```

The MongoDB database backup consists of a compressed file (`.gz`) located under `/opt/stream/var/backup/`.

To run a complete backup, execute the following command:

```
# /opt/stream/sbin/stream-backup -c -d
```



- The backup output folder can be overridden using the `-o` | `--output` parameter
- The backup tool can operate in quiet mode (when scheduled in a cron job) using the `-q` | `--quiet` parameter
- If you want to encrypt your back-up files, use the `-e` | `--encrypt` parameter. The backup tool will prompt you for a passphrase. The back-up will be encrypted using AES-256.

## Restoration Procedure

This section details how to restore a Stream back-up that was generated using the `stream-backup` tool. The restoration happens using the `stream-restore` tool.

```
# /opt/stream/sbin/stream-restore --help
```

Stream restore tool usage: `stream-restore`

- a | --archive [filepath] The encrypted backup file to restore
- c | --conf [filepath] The path to the Stream configuration backup file
- d | --db [filepath] The path to the Stream database backup file
- m | --mongo\_uri [MongoDB URI] The MongoDB URI to back-up the database into (optional)
- h | --help Displays the 'stream-restore' help
- q | --quiet Quiet mode

Whenever trying to restore a backup, you need to stop the Stream service first:

```
# systemctl stop stream
```

To restore an unencrypted configuration backup, run the following command:

```
# /opt/stream/sbin/stream-restore -c [configuration backup archive path]
```

To restore an unencrypted MongoDB database backup, run the following command:

```
# /opt/stream/sbin/stream-restore -d [MongoDB backup archive path] -m [MongoDB URI]
```

The MongoDB URI is optional: if not provided, the script will try to infer it from the `/etc/default/stream` file. If it cannot be inferred and none is provided, the restore will fail.

To restore an encrypted backup archive, run the following command:

```
# /opt/stream/sbin/stream-restore -a [encrypted backup archive path] -m [MongoDB URI]
```

The restoration tool will prompt you for the passphrase that was used to encrypt the backup. If the archive contains only a configuration backup, the script will perform the equivalent of the `-c` parameter. If the archive contains only a database backup, the script will perform the equivalent of the `-d` parameter, and you might need to provide the MongoDB URI through the `-m` parameter. If the archive contains both a database and a configuration backup, both of them will be restored.

When the restoration is complete, you can start Stream again using the following command:

```
# systemctl start stream
```

## 2.13. Dictionaries

Here is the list of available dictionary keys to use in computation rules and template strings, depending on the usage.

### Certificate Authority

This dictionary regroups the information of a Certificate Authority.

Key	Description	Type
ca.name	The technical name of the ca	Single value
ca.type	The type of ca (managed or external)	Single value
ca.signer	The values from the signer	Signer dictionary

### OCSP Signer

This dictionary regroups the information of an OCSP signer.

Key	Description	Type
ocsp.name	The technical name of the ocsp signer	Single value
ocsp.signer	The values from the signer	Signer dictionary

### Timestamping Authority

This dictionary regroups the information of a Timestamping authority.

Key	Description	Type
tsa.name	The technical name of the timestamping signer	Single value
tsa.signer	The values from the signer	Signer dictionary

### CRL

This dictionary regroups the information of a CRL.

Key	Description	Type
crl.ca.name	The technical name of the ca that signed the CRL	Single value
crl.ca.type	The type of the ca that signed the CRL	Single value

Key	Description	Type
crl.number	The CRL number	Single value
crl.this_update	The value of this_update	Single value
crl.next_update	The value of next_update	Single value
crl.next_refresh	The value of next_refresh	Single value
crl.size	The number of certificates in the crl	Single value
crl.eidas	"true" if the CRL is eidas compliant, else "false"	Single value
crl.error	The value of the error if the CRL generation failed	Single value

## Credentials

This dictionary regroups the information of a Credential.

Key	Description	Type
credentials.name	The credentials name	Single value
credentials.description	The credentials description	Single value
credentials.expires	The credentials expiration date	Single value
credentials.type	The credentials type	Single value
credentials.target	The credentials target	Single value

In a rest notification, headers can be enriched using the credentials values:

Key	Description	Type
credentials.login	The credentials login value for Password Credentials	Single value
credentials.password	The credentials password value for Password Credentials	Single value
credentials.secret	The credentials secret value for Raw Credentials	Single value

## License

This dictionary regroups the information of the Stream license.

Key	Description	Type
license.expires	The license expiration date	Single value
license.modules	The enabled modules	Single value

## Sub dictionaries

These dictionary cannot be used alone but can be completed with one of the other ones. For example, a valid key is:

```
ocsp.signer.dn.cn.1
```

## Signer dictionary

Key	Description	Type
dn	The full dn of the certificate in TYPE=value form	Single valued
dn.<dn field type>	All values of subject field of type <b>dn field type</b>	Multi valued
dn.<dn field type>.<index>	Value of subject field of type <b>dn field type</b> at index <b>index</b>	Single value
sans.<sans field type>	All values of subject field of type <b>sans field type</b>	Multi valued
sans.<sans field type>.<index>	Value of subject field of type <b>sans field type</b> at index <b>index</b>	Single value
issuer	The full dn of the issuer of the certificate in TYPE=value form	Single valued
not_before	Value of the start date of the certificate	Single value
not_after	Value of the expiration date of the certificate	Single value
serial	The certificate serial	Single valued
thumbprint	The certificate thumbprint	Single valued
public_key_thumbprint	The certificate public key thumbprint	Single valued
key_type	The certificate key type	Single valued
signing_algorithm	The certificate signing algorithm	Single valued
pem	The PEM encoded certificate	Single valued



The valid dn field types are: cn, uid, serialnumber, surname, givenname, unstructuredaddress, unstructuredname, e, ou, organizationidentifier, uniqueidentifier, street, st, l, o, c, description, dc.



The valid san field types are: rfc822name, dnsname, uri, ipaddress,

othername\_upn, othername\_guid.



All indexes start at 1

## 2.14. Computation rule

Computation Rules are expressions that describe operations to apply to dictionary keys. These keys can come from diverse data sources such as a certification request or a user entry. The available operations and their usage are detailed in this part.

### Example

Let's start by an example:

My CSR contains a DNSNAME subject alternate name with the following value:

```
host.evertrust.fr
```

I want my final certificate to have 2 SANs, this value and its short name: "host".

In order to do that, in **Profile** › **Certificate Template** › **Subject Alternate Names**, I add a DNSNAME SAN with the following computation rule:

```
[{{csr.san.dnsname.1}}, Extract({{csr.san.dnsname.1}}, "(.*?)\.", 1)]
```

This will output, in my final certificate, two SANs with values:

```
host.evertrust.fr, host
```

To explain this result, the value "host.evertrust.fr" was retrieved by choosing the first DNSNAME SAN of the CSR: `{{csr.san.dnsname.1}}`. The function `Extract` extracted the first catching group from the regex `(.*?)\.`, resulting in the "host" value.

The computation rule language has a lot more possible operations, allowing complex use cases to become reality.

### Dictionary keys

Dictionary keys are a way to name the information from the available sources. For instance, for a webra enroll, the available sources are the given csr, the webra enroll form data and the principal information if it is authenticated. The full list of available dictionary keys is available on the dictionary page.

## Enrollment

A key can reference a single element or a list of elements. It is separated in three main parts: the source of data (csr, webra enroll data form), the section of the data, and an optional number

For example, the following is a valid key with these 3 parts:

```
{{csr.subject.cn.1}}
```

The csr is the data source, the subject.cn the requested information and the 1 is the index. It allows to retrieve the first, common name from the subject, from the CSR.

Without an index, the key is still valid, but it will output all the corresponding values. For example

```
[[csr.subject.ou]]
```

This retrieves all the ou from the subject, from the CSR.



When a key is expected to output a single value it should be written as a single dictionary key, and one outputting a list of values as a multi dictionary key, otherwise it will be none.

## Basic expressions

### Basic string expressions

The following expressions are evaluated as a string or None.

Expression Name	Syntax	Allowed Values	Description	Example
Single dictionary key	{{<key>}}	key: a-zA-A-._	This retrieves a key value from the dictionary, none if it does not exist	{{csr.subject.cn.1}}
Number	<number>	number: -\d+	This will output the given number	-4
Literal	"<literal>"	literal: any string	This will output the given literal	"iAmAString"
Null	NULL	NULL	This will output None	NULL
Now	NOW	NOW	This will output the current instant	NOW

### Basic list expressions

The following expressions are evaluated as a list of string or None.

Expression Name	Syntax	Allowed Values	Description	Example
Multi dictionary key	[[<key>]]	key: a-zA-A-._	This retrieves all values that start with key from the dictionary	[[admin-guide:computation_rules:::csr.subject.cn]]
Array	[<simpleExpression>, ... <simpleExpression>]	simpleExpression: any expression that will be evaluated to a single element	This will output a multi expression composed of all inserted simple expressions	["iAmAString", {{csr.san.dnsname.1}}]

## Quick reference



Function names are not case sensitive but keys are

Function Name	Syntax
Upper	Upper(expression: <expression>)
Lower	Lower(expression: <expression>)
Trim	Trim(expression: <expression>)
Substr	Substr(expression: <expression>, start: <number>)
Substr	Substr(expression: <expression>, start: <number>, end: <number>)
Concat	Concat(expression: <expression>, ... <expression>)
Extract	Extract(expression: <expression>, regex: <literal>)
Extract	Extract(expression: <expression>, regex: <literal>, group: <number>)
Replace	Replace(expression: <expression>, regex: <literal>, replacement: <expression>)
OrElse	OrElse(expression: <expression>, ... <expression>)
Match	Match(expression: <simpleExpression>, regex: <literal>)
DateTimeFormat	DateTimeFormat(expression: <simpleExpression>, format: <literal>)
Get	Get(expression: <multiExpression>, index: <number>)
First	First(expression: <multiExpression>)
Last	Last(expression: <multiExpression>)

Function Name	Syntax
Filter	Filter( <b>expression</b> : <multiExpression>, <b>regex</b> : <literal>)
Slice	Slice( <b>expression</b> : <multiExpression>, <b>start</b> : <number>)
Slice	Slice( <b>expression</b> : <multiExpression>, <b>start</b> : <number>, <b>end</b> : <number>)

## Any expression functions

### Upper

```
Upper(expression:<expression>)
```

This outputs the result evaluated from **expression** with only upper case characters and None if no value was evaluated

```
Upper("string") => "STRING"
Upper(["string1", "string2"]) => ["STRING1", "STRING2"]
```

### Lower

```
Lower(expression:<expression>)
```

This outputs the result evaluated from **expression** with only lower case characters and None if no value was evaluated

```
Lower("STRING") => "string"
Lower(["STRING1", "STRING2"]) => ["string1", "string2"]
```

### Trim

```
Trim(expression:<expression>)
```

This outputs the trimmed result evaluated from **expression** and None if no value was evaluated

```
Trim(" STRING") => "STRING"
Trim(["string1 ", " string2 "]) => ["string1", "string2"]
```

## Substr

```
Substr(expression: <expression>, start: <number>)
```

This outputs the substring from index **start** to the end of the string evaluated from **expression** and **None** if no value was evaluated or the result of substring is empty. **start** can be negative and it will be computed from end of string.

```
Substr("STRING", 2) => "TRING"  
Substr(["string", "longerString", "s"], -2) => ["ng", "ng", "s"]  
Substr("tooShort", 15) => None
```

## Substr

```
Substr(expression: <expression>, start: <number>, end: <number>)
```

This outputs the substring from index **start** to **end** of the string evaluated from **expression** and **None** if no value was evaluated or the result of substring is empty. **start** and **end** can be negative and it will be computed from end of string.

```
Substr("STRING", 2, 4) => "TRI"  
Substr(["string", "longerString", "s"], 2, -2) => ["tri", "ongerStri"]  
Substr("tooShort", -2, 4) => None
```

## Concat

```
Concat(expression: <expression>, ...<expression>)
```

This outputs the concatenation of evaluated expressions: if they are all simple expression, a string concatenation will take place, otherwise an array with all the values will be evaluated. If the final result is empty, **None** will be returned.

```
Concat("start", " middle ", "end") => "start middle end"  
Concat(["string1", "string2", "string3"], "string4") => ["string1", "string2",  
"string3", "string4"]
```

## Extract

```
Extract(expression: <expression>, regex: <literal>)
```

This extracts from the evaluated **expression** string(s) the part that matches the **regex**

```
Extract("abcd@domain.com", ".*@") => "abcd@"  
Extract(["string1", "string2", "string3"], "\d") => ["1", "2", "3"]
```

## Extract

```
Extract(expression: <expression>, regex: <literal>, group: <number>)
```

This extracts from the evaluated **expression** string(s) the group at index **group** that matches the **regex**

```
Extract("abcd@domain.com", "(.*)@", 1) => "abcd"  
Extract(["string1", "string2", "string3"], "(.*)\d", 1) => ["string", "string",  
"string"]
```

## Replace

```
Replace(expression: <expression>, regex: <literal>, replacement: <expression>)
```

This replaces parts of the evaluated **expression** string(s) that matches the **regex** with the evaluated **replacement**. If **replacement** is None, values will be replaced by an empty string.

```
Replace("abcdATdomain.com", "AT", "@") => "abcd@domain.com"  
Replace(["string1", "string2", "string3"], "\d", CONCAT("This", " was ", " a number"))  
=> ["stringThis was a number", "stringThis was a number", "stringThis was a number"]
```

## OrElse

```
OrElse(expression: <expression>, ...<expression>)
```

This outputs the first non None result of the given expressions, or None if they are all None

```
OrElse({{not.a.value}}, "abcd@domain.com") => "abcd@domain.com"  
OrElse([[no.values]], "value") => ["value"]  
OrElse([[no.values]], {{not.a.value}}) => None
```

## String functions



The following functions output a string or None.

## Match

```
Match(expression: <simpleExpression>, regex: <literal>)
```

This outputs the expression if it matches the regex, otherwise None

```
Match("abcd", "[a-z]+") => "abcd"  
Match("abcd", "\d+") => None
```

## DateTimeFormat

```
DateTimeFormat(expression: <simpleExpression>, format: <literal>)
```

This outputs the expression formatted as format. If expression is not a date, no formatting takes place. Available formats are:

- Custom format in Java DateFormatter syntax
- MILLIS
- BASIC\_ISO\_DATE
- ISO\_LOCAL\_DATE
- ISO\_OFFSET\_DATE
- ISO\_DATE
- ISO\_LOCAL\_TIME
- ISO\_OFFSET\_TIME
- ISO\_TIME
- ISO\_LOCAL\_DATE\_TIME
- ISO\_ZONED\_DATE\_TIME
- ISO\_DATE\_TIME
- ISO\_ORDINAL\_DATE
- ISO\_WEEK\_DATE
- ISO\_INSTANT
- RFC\_1123\_DATE\_TIME

```
DateTimeFormat(NOW, "MILLIS") => "1709290260764"  
DateTimeFormat(NOW, "hh:mm:ss") => "10:54:57"
```

## Get

```
Get(expression: <multiExpression>, index: <number>)
```

This outputs the string at `index` index in the `expression` list, and `None` if the index does not exist. The index can be negative to get from the end of the list.

```
Get(["string1", "string2", "string3", "string4"], -2) => "string3"  
Get(["string1", "string2"], 3) => None
```

## First

```
First(expression: <multiExpression>)
```

This outputs the first string of the `expression` list, and `None` if it does not exist. The index can be negative to get from the end of the list.

```
First(["string1", "string2", "string3", "string4"]) => "string1"  
First([[no.values]]) => None
```

## Last

```
Last(expression: <multiExpression>)
```

This outputs the last string of the `expression` list, and `None` if it does not exist. The index can be negative to get from the end of the list.

```
Last(["string1", "string2", "string3", "string4"]) => "string4"  
Last([[no.values]]) => None
```

## List of string functions



The following functions output a list of string or `None`.

## Filter

```
Filter(expression: <multiExpression>, regex: <literal>)
```

This outputs a list of string from `expression` that matches the `regex`, `None` if none matches

```
Filter(["string1", "string2", "match"], "[a-z]+") => ["match"]
Filter(["string1", "string2"], "[a-z]+") => None
```

## Slice

```
Slice(expression: <multiExpression>, start: <number>)
```

This outputs the slice of the **expression** list between **start** index and its end, or None if the slice is invalid. The index can be negative to get from the end of the list.

```
Slice(["string1", "string2", "string3", "string4"], -2) => ["string3", "string4"]
Slice(["string1", "string2"], 3) => None
```

## Slice

```
Slice(expression: <multiExpression>, start: <number>, end: <number>)
```

This outputs the slice of the **expression** list between **start** and **end** index, or None if the slice is invalid. The index can be negative to get from the end of the list.

```
Slice(["string1", "string2", "string3", "string4"], 1, 3) => ["string1", "string2",
"string3"]
Slice(["string1", "string2"], 3) => None
```

## 2.15. Template Strings

Template Strings are augmented strings. They can be used as normal text but can also be augmented:

### Using dictionary values

Using the following format, a dictionary key will be interpreted to its value when sending the notification:

```
{{<dictionary key>}}
```

Example:

```
I am enrolling on {{ca.name}}
```

Depending on the notification event, values will be added to context to be interpreted.



If the value is not available in the context, the dictionary value will not be replaced

## Using computation rules

Using the following format, a computation rule will be interpreted to its value when sending the notification:

```
{{<computation rule>}}
```

Example:

```
I am enrolling on {{ Lower({{ca.name}}) }}
```

Depending on the notification event, values will be added to context to be interpreted in the computation rule.



If the computation rule result is None, an empty string will be displayed. If it is an array, it will be in a comma separated string

## 3. Release notes

### 3.1. Stream 2.1.1 release notes

Here are the release notes for EverTrust Stream v[object Object], released on 2025-06-17.

For the installation and upgrade procedure, please refer to the Installation and Upgrade guide.



The Akka framework has been replaced by Pekko. It can lead to configuration changes if you manually manage the Stream configuration.

## New Features

[None]

## Enhancements

- [STM-1214] - Added support for the SLH DSA PQC algorithm
- [STM-1174] - S3 RL storages now include an option to specify the expected checksum verification
- [STM-1205] - Revoking an expired certificate is now treated as a successful operation via the API
- [STM-1208] - Added a default configuration for Mongo lease settings

## Bug Fixes

- [STM-1229] - Fixed an issue that caused crashes when interacting with the PKCS#11 library
- [STM-1233] - Fixed a bug where NTP requests failed when `maxOffset` was set and a 0 ms offset was returned
- [STM-1207] - `lifecycle:*` permissions are now correctly migrated
- [STM-1211] - Aligned signature algorithm format with industry standards when signing RSA certificates using PKCS#11
- [STM-1227] - `stream-upgrade` now properly ignores commented lines in the `/etc/default` file
- [STM-1231] - Properly handles migration of the Mongo URI during RPM upgrades
- [STM-1175] - Fixed missing fields during SSH CA creation
- [STM-1190] - Fixed missing fields when editing templates

## Known Defects

[None]

## API Modifications

[None]

## 3.2. Stream 2.1.0 release notes

Here are the release notes for EverTrust Stream v[object Object], released on 2025-04-30.

For the installation and upgrade procedure, please refer to the Installation and Upgrade guide.



The Akka framework has been replaced by Pekko. It can lead to configuration changes if you manually manage the Stream configuration.

## New Features

- [STM-772] - Added support for MLDSA and hybrid certificates (Catalyst / Chimera / AltPubKey)
- [STM-378] - Introduced support for SSH certificates
- [STM-919] - Implemented keystore health checks. Status can now be used to influence readiness in HA environments. [Learn more ...](#)

## Enhancements

- [STM-896] - Reorganized technical configuration parameters for improved structure and clarity. [Learn more ...](#)
- [STM-842] - A description can now be added on Certificate Authorities
- [STM-890] - Enabled notifications on CRL Sync Error

- [STM-1053] - Added support for the Title RDN attribute
- [STM-782] - Changed database driver. Stream Mongo URI can now be used with mongosh.



Some connection options in Mongo URI are no longer available: `keyStore`, `keyStorePassword`, `keyStoreType`. If these are used, please contact the EVERTRUST support for migration steps.

## Bug Fixes

- [STM-592] - Available dynamic attributes on RL Storages are now properly displayed
- [STM-893] - Stream RL Storage now correctly updates `nextRefresh` when using lazy CRL generation
- [STM-921] - Fixed an issue where DN elements had to be capitalized in notification dynamic attributes and RL storage configurations
- [STM-1131] - Resolved a bug that prevented authorizations containing a `/` from opening in the Web UI
- [STM-1154] - Fixed an issue where DN elements with trailing spaces could not be enrolled correctly

## Known Defects

- [STM-1174] - AWS SDK now enforces checksum by default, which may not yet be supported by S3 providers other than AWS. To fix the issue, env variables `AWS_REQUEST_CHECKSUM_CALCULATION=when_required` and `AWS_RESPONSE_CHECKSUM_CALCULATION=when_required` must be set. This behavior will be configurable for each S3 in future releases
- [STM-1207] - Lifecycle permissions on all Certificate authorities (`lifecycle:*:...`) are not migrated correctly and lead to invalid permissions, that can result in denied requests. To fix this issue, you will need to delete the old permission and replace it with the new permission `lifecycle:x509:*`
- [STM-1229] - Updating a PKCS#11 keystore can result in an application crash
- [STM-1231] - RPM upgrade logs errors due to an error in mongo url automatic migration. If your uri does not contain specific options, it will not have any impact

## API Modifications

- [STM-772] - The `description` field in a `PrivateKey` object (to create a key, or returned from keystore list operations) is now a `string enum` instead of an `object`